

# **JMap Admin 7**

## **Administrator Manual**



# Table of contents

Introduction	1
Quick Start Guide .....	1
User Interface .....	3
Databases	7
Creating Databases .....	7
Configuring and Managing Databases .....	9
SQL Console .....	11
JMap Server to JMap Server Connections	13
Spatial Data Sources	18
Creating Spatial Data Sources .....	21
Configuring Spatial Data Sources .....	22
Vector Data Sources .....	24
JMap ADF / E00 Arc / Info reader .....	26
JMap CSV reader .....	26
JMap DGN V7 / V8 File reader .....	27
JMap DWG / DXF reader .....	27
JMap EDIGEO reader .....	28
JMap File geodatabase (ESRI) reader .....	29
JMap GeoJSON reader .....	29
JMap GML reader .....	30
JMap GPX reader .....	30
JMap IFC reader .....	31
JMap KML reader .....	31
JMap MID / MIF reader .....	32
JMap SHP reader .....	32

# Table of contents

JMap TAB reader .....	33
Annotations in a database .....	33
ArcGIS REST .....	34
ArcSDE geodatabase (ESRI ArcGIS 10.0 and earlier) .....	35
Coordinates in a database .....	36
Enterprise geodatabase (ESRI ArcGIS 10.1 and later) .....	37
JMap Server .....	39
MySQL Spatial .....	39
JMap Spatial Table .....	40
Oracle Spatial / Locator .....	41
Personal geodatabase (ESRI) .....	42
PostGIS .....	43
SQL Server Spatial .....	44
WFS Server .....	45
WKB or WKT in a database .....	46
Raster Data Sources .....	47
ECW / JPG2000 .....	47
GDAL (Geospatial Data Abstraction Library) .....	48
TIFF / GEOTIFF .....	49
ArcGIS REST .....	50
JMap Server .....	50
OpenStreetMap (OSM) .....	51
WMS server .....	51
WMTS Server .....	52
Spatial Data Source Permissions .....	53

# Table of contents

Sharing Spatial Data Sources .....	53
External Attributes .....	54
Metadata .....	56
Projects .....	59
Creating Projects .....	59
Configuring Projects .....	62
Managing Projects .....	65
Project Permissions .....	66
Multilingual Projects .....	67
Organizing Layers .....	68
Attribute Queries .....	73
Style Templates .....	76
Personal Layers .....	78
Layers .....	79
Creating Layers .....	81
Configuring Layers .....	87
Layer Permissions .....	89
Sharing Layers .....	90
General Settings .....	92
Dynamic Filters .....	94
Style .....	95
Thematics .....	101
Labels .....	110
Mouseover .....	114
Information Reports .....	122

# Table of contents

Forms .....	128
Form Designer .....	129
Layer Attributes Forms .....	139
Database Forms .....	140
Attribute Query Forms .....	144
JMap Extensions .....	146
Deploying JMap Applications .....	148
JMap Pro Applications .....	150
JMap Web Applications .....	153
JMap Mobile Applications .....	162
WFS and WMS Services .....	164
Managing Deployed Applications .....	165
Using a GeoWebCache Server .....	167
Security .....	171
Managing Users .....	171
Managing User Accounts and Groups .....	175
Managing Permissions .....	177
Single Sign-On .....	182
Managing Sessions .....	182
Using HTTPS with JMap .....	184
JMap Server Management .....	186
JMap Server Status .....	186
Exporting and Importing .....	188
User Data .....	190
JMap Server Settings .....	191

# Table of contents

Usage Statistics .....	195
Log Files .....	198
Messages .....	199
JMap Server System Database .....	200
Backups .....	201
High Availability .....	203

## Introduction

JMap is a map-based integration platform. It offers a quick way to connect all systems and consolidate all data belonging to an organization. All the information is then published on a map. By providing real-time access to all data on a single interface, JMap enables managers, GIS analysts and non-technical users to make better decisions and take action quickly.

As an integration platform, JMap solves issues related to the lack of interoperability within certain organizations. A neutral platform, JMap can connect to any system or IT environment without disrupting what is already in place.

As a map-based platform, JMap provides its users with a series of GIS tools, which are available as desktop, web or mobile applications.

JMap Server is managed in its entirety through the JMap Admin application. This web interface allows administrators to perform tasks such as integrating databases, creating projects, disseminating maps, and managing security.

This manual explains how to use JMap Admin to administrate a JMap environment.

## Quick Start Guide

---


The following walk-through guide describes the major steps for configuring and publishing a map with JMap.

Make sure JMap Server is running. If it was installed as a service on Windows, you must start it using the Windows Services window. Otherwise, it must be started using the executables in JMAP\_HOME/bin or using the shortcuts created during the installation on the server.

To open JMap Admin, you can use the shortcut that was created during the installation inside the installation home directory, on the server. You can also open a web browser and type a URL similar to <http://192.168.0.1:8080/jmapadmin>. The IP address and port number may vary depending on the installation environment and chosen parameters.

Once JMap Admin is open, you will be prompted for a username and password. The default login after the installation is username "administrator" and the password field is empty.

In JMap Admin, you will need to follow the steps below in order to publish map data.



## Step 1 — Creating spatial data sources

This step requires that you define your spatial data sources. These can be GIS files, spatial data servers, satellite images, etc. When doing so, you indicate to JMap where to read your data from.

See section [Creating Spatial Data Sources](#) for more information.

## Step 2 — Creating a project

A project in JMap contains map layer definitions data along with parameters regarding access controls (security), queries, units, etc. By creating a project, you define what information your map will contain and what it will look like.

See section [Creating Projects](#) for more information.



## Step 3 — Creating layers in the project

At this step, you create the map layers for your new project. Each map layer is associated with a spatial data source. For each layer, you must define the style (how the layer elements will be drawn), labels, thematics, etc. You can also define access control on a layer by layer basis.

See section [Creating Layers](#) for more information.

## Step 4 — Deploying an application

This is the last step. Here you publish your project using the application template of your choice. Each application template offers different levels of functionality. There are templates for desktop, web and mobile applications. Once your application is deployed, users can start using it to navigate your map data.

See section [Deploying JMap Applications](#) for more information.

## User Interface

The following screen captures show the graphical user interface of JMap Admin. The different parts of the interface are described below.

The screenshot displays the JMap Admin interface. At the top, the 'Status' header includes the JMap Admin logo, 'JMap Server', and user information 'Administrator'. A navigation bar contains 'JMap 7 - DEMO', 'EN', 'Help', and 'Administrator'. The left sidebar features icons for settings, home, and other functions. The main content area is split into two columns. The left column, labeled 'General', contains a table with server details: Version (JMap Server version 7.0 (7.0.0)), IP Address (WIN-SHU4LMQJ6ER (10.4.164.17)), Port (7005), and Server cluster (No). Below this is a 'Sessions' section showing 'Total active sessions' as 3 and 'Active JMap Pro sessions' as 0 / Unlimited. The right column, labeled 'License information', contains a table with license details: Model (Session-restricted license), Licensed to (K2-JMap 7.0 Demo), Serial number (7372-4357-0931), and various session limits (Unlimited for Pro, Web, and Mobile sessions; Authorized for JMap Server sessions; Unlimited for Maximum projects).

- 1 You can specify the name of the JMap Server.

The Help menu allows you to access this manual, the manuals of the extensions installed on the server, and the K2 Geospatial Knowledge Base.


You can select the display language of JMap Admin. The language chosen in this menu as well as the language chosen in the connection interface is saved by JMap, which displays it by default in subsequent sessions.

The user account name of the JMap Admin session. You can change the account password and log out of the session.


- 2 The sidebar allows you to access the main sections of JMap Admin.
- 3 The menu varies depending on the context and allows you to open the subsections.
- 4 Shortcut buttons allow you to access a specific section quickly.

The screenshot displays the JMap Admin interface for 'Spatial data'. The header includes 'JMap 7 - DEMO', 'EN', and 'Help'. The main content area shows a table of spatial data resources with columns for NAME, STATUS, DATA SOURCE TYPE, PROJECTION, ELEMENTS, and LAST UPDATE TIME. A search filter 'Montr' is applied to the NAME column. A filter menu is open on the right, showing options like 'Hide not accessible by me', 'Hide not owned by me', and 'Show system data sources'. The table lists several resources, including 'Montreal - Affectation du sol', 'Montreal - Arceaux a velos', 'Montreal - Batiments vacants', 'Montreal - Bornes de stationnement', 'Montreal - Zone revitalisation urbaine integree (RUI)', and 'Montreal Ortho 2005 Ecw'. The bottom of the table shows '19 / 19' items and a '30 Items per page' dropdown.

- 1 Lists allow you to select items.
- 2 List options allow you to select the fields displayed in the list.
- 3 Filters for certain fields allow you to filter the contents of the list.
- 4 You can navigate through the pages of the list or modify the number of items per page.
- 5 The search tool allows you to locate resources by name in JMap Admin.



- 1 A breadcrumb trail allows you to navigate through JMap Admin.
- 2 The administrator manual can be accessed via the Help menu.



- 1 When this button is displayed, it indicates that you can add translations for the various languages you want the system to support.
- 2 Each resource can be translated into several languages.

**Project Configuration**  
Projects > Montreal (EPSG:3857)

JMap 7 - DEMO EN Help

Edit Delete

### General information

Name	Montreal (EPSG:3857)
Id	5
Description	
Default language	French
Available languages	French English Spanish

### Project settings

Map projection	WGS 84 / Pseudo-Mercator - EPSG:3857		
Map unit	Meters		
Distance unit	Meters		
Display unit	Meters		
Extent	X	Y	
	-20,039,512.09	-20,039,512.09	
	Width	Height	
	40,079,024.19	40,079,024.19	

### Initial view settings

Minimum scale	1: Infinity
---------------	-------------

### Preview

1

2

### Layers

STATUS

- 1 JMap Admin provides a preview of each project at all times, as you make changes to it.
- 2 You can open your project with JMap Web or JMap Pro without leaving JMap Admin.

## Databases

JMap Server manages database connections by placing them in pools. The pools contain a certain number of open database connections. These connections are shared with the entire system and used according to database access needs.

All the database connection pools (hereafter called databases for simplicity) are centrally managed using JMap Admin. Databases are typically used by JMap Server to read spatial data stored in tables and to access descriptive data related to spatial data. Once databases are configured in JMap Admin, they can be used from other sections and for various purposes in the administration process.

The Databases section in JMap Admin is used to display a table of existing databases and to show their statuses.

### System Database

JMap has a System database that contains JMap Server's configurations and geometry tables. This database is mandatory and generally should not be modified. It cannot be deleted and should only be manipulated by advanced users. See section [JMap Server System Database](#) for more information.

## Creating Databases

To start creating a new database connection, press the **Create** button in the page listing the databases and follow the required steps.

Identification	
Name	Enter a name for the new database. The name must be unique.
Description	Optionally enter a description for the new database. The description can only be viewed by administrators in JMap Admin.

Connection parameters	
Driver	Select the driver for the database system you wish to connect to. You can add new drivers by creating new configuration files in the JMAP_HOME/conf/db directory on the server.
Host	(Depending on the selected driver) The name or TCP/IP address of the database server.

Port	(Depending on the selected driver) The TCP/IP port of the database server.
Database	(Depending on the selected driver) The name of the database to access, as defined in the database server.
Folder	(Depending on the selected driver) The path to the database folder.
Extra parameters	In some rare cases, database systems may require additional parameters. They can be entered in this field.
Username	Enter a username for the database connection. The authentication of domain users is not supported; you must make sure your database allows database authentication.
Password	Enter a password for the database connection.

<b>Connections</b>	
Number of connections	Enter the initial size of the pool of connections. This determines how many connections to the database will be kept open.
Maximum connections	<p>Enter the maximum number of connections allowed for this pool. It must be equal to or greater than the initial number of connections. If the pool needs to be increased, new database connections will be created automatically until the maximum value is reached. After a certain period of time, additional connections are automatically closed, and the connection pool returns to its initial size.</p> <p>The maximum value can be disabled by unselecting the check box, allowing the pool to increase without restriction.</p>

## Advanced parameters

The following advanced parameters usually don't need to be modified.

<b>Parameters</b>	
Additional parameters	In some rare cases, database systems may require additional parameters. They can be entered in this field.
Validation query	JMap uses a query validation mechanism to validate database connections. This query is used to test the connection each time a query needs to be executed. If the validation query fails, which typically means

	<p>that the connection to the database is broken, JMap Server will try to establish a new connection automatically. This mechanism ensures the database connections are always working.</p> <p>The query must be valid and very quick to execute. In order to reduce the impact on performance, make sure you minimize the number of returned records (zero is perfect) and use indexed fields in the WHERE clause.</p> <p>Default queries are provided. They normally don't need to be changed.</p>
Connection timeout	<p>The connection inactivity timeout is used to close and reopen connections that are inactive for a long period. This mechanism ensures that the database system does not close inactive connections. Make sure that this value is lesser than the connection timeout of your database system. A default value of 2 hours is appropriate most of the time.</p>
Connection wait timeout	<p>The maximum wait time when opening a network connection to a database. This parameter is used to prevent deadlocks in situations where the database server is not responding. The default value is 60 sec. Enable this option to specify a different value for this connection.</p>
Connection type	<p>Specify the connection type to create. Generic connections are all created with the same user information (username and password) defined earlier. From the perspective of the database system, it is as if the same user performed all queries. This type of connection is used most of the time.</p> <p>Identified connections are created on the fly for each user connected to JMap Server. The same connection is reused during the session for each user. From the perspective of the database management system, each query is done by the user who is connected to JMap Server. This connection mode is useful in environments where security is managed at the database level. In order for the identified connection mode to work, it is required that JMap and the database system share the same list of users. This can be the case when the Oracle user manager module is used to manage users.</p>

## Configuring and Managing Databases

When you click on the name of a database in the **Database** section, the **Database configuration** interface displays.

This interface has buttons to **Edit**, [Reinitialize](#), [Deactivate](#) or [Delete](#) the database. The  button allows you to access the [SQL Console](#) and [Permissions](#) sections.

Several subsections display information on the database. The parameter values indicated were defined when the database connection was created. Refer to [Creating Databases](#) for the details of each parameter. These parameters can be modified by clicking on **Edit**.

## General information

This subsection displays the name, Id (internal JMap identifier), a description, and the database owner.

## Database connection pool

This subsection displays the details of the connection pool. The parameters indicated are the following: Initial size, Maximum size, Pool usage, Pool usage peak, Connection timeout, and Connection wait timeout.

## Database connection

This subsection displays the details of the database connection. The parameters indicated are the following: [Status](#), Database (indicates the type), Driver, Connection string, Username, Validation query, and Connection type.

## References

This subsection shows all the resources using the data from the database. The information in this section is presented hierarchically and displays the spatial data sources as well as the projects with the layers, reports, and forms, all showing the attributes used. This can be useful to view the resources that would be affected by changes made to the database.

## Reinitializing databases

Reinitializing a database closes all open connections and creates new ones. This can be useful to force a reconnection to a database system.

## Deactivating databases

Deactivating a database closes connections to the database without deleting its configuration. JMap Server can no longer query the database. Deactivating is useful when the database stops responding and causes delays in the local server.

## Deleting databases

Deleting a database deletes the connection configuration for the database system. The data contained in the database is not affected at all.



## Database statuses


Each database has a status. The status indicates the condition of the database connection. The following table describes the possible statuses of a database.

Statuses	
Error	The database connections are broken. The database cannot be used until the error is resolved and the connections are reopened. Reinitializing the database might correct the problem. You can view a description of the error by clicking on the word <b>Error</b> displayed in red.
Inactive	The database connections are closed but they are configured. JMap can no longer query the database.
Connected	The database connections were created successfully and are ready to be used.

## SQL Console

JMap Admin provides a generic SQL console that can be used to view database structures, execute SQL queries, inspect the content of tables, test for query execution speed, etc. All configured databases are accessible through this console.

When performing an SQL query, the query execution is subject to security permissions granted to the user connected to the database. See [Creating Databases](#) for more information about specifying the user for database connections.

SQL console	
Database	Select the database to use.
View structure	Click on  to open a window that allows you to navigate in the structure of the database. You can see the schemas, the tables and views, and information about each field of a table or view.
Max. rows	When executing a Select SQL query, you can enter a value to limit the number of returned rows.
Auto commit	If performing SQL transactions (e.g. Insert, Update), select this option to validate the transactions automatically (SQL COMMIT command). Otherwise, you will need to perform the validations manually.

Test for speed only	When executing an SQL query, select this option to repeat the query a certain number of times and display the execution times.
SQL Query	Enter the SQL query to execute. The result will be displayed in a table.

Query results are displayed in a new window. The results of the Insert, Update, and Delete requests are grouped in the same tab. The results of Select type queries appear in separate tabs.


## JMap Server to JMap Server Connections

It is possible to create connections from one JMap Server to another. These connections can then be used to share layers and spatial data sources between different JMap Servers while avoiding duplication of source data. They may also be used by some JMap Server extensions that require server to server communication. These connections are used, among other things, when creating [JMap Server vector](#) or [JMap Server raster](#) data sources and when using shared layers.

JMap Server manages connections towards other JMap Servers by placing them in pools.

Note that your JMap user license must allow server sessions in order for another JMap Server to connect to your JMap Server. For more information, refer to the [JMap Server Status](#) section.

The following diagram shows the connection between two JMap Servers (A and B) where the JMap application connected to server A accesses spatial data served by another JMap Server instance (server B).



Connection between 2 JMap Server instances

## Creating Connections to JMap Server

To start creating a new connection, click on the Create button in the page listing the connections and follow the required steps.

Identification	
Name	Enter a name for the new connection. The name chosen must be unique.

Configuration	
Connection type	Select the method used to connect to the remote server, either direct or proxy. This option may depend on the network configuration on the remote server side. Proxy connections use the HTTP protocol and therefore pass through firewalls easier.  The parameters to enter will depend on the type of connection selected.
Host	Enter the name or IP address of the remote server to which you wish to connect.
Server port	(Direct connection) If you are creating a direct connection, enter the port used to establish the connection towards JMap Server.
Protocol	(Proxy connection) If you are creating a proxy connection, select the HTTP or HTTPS (secure) protocol used by the connection.
Relative path	(Proxy connection) If you are creating a proxy connection, enter the relative path to reach the JMap proxy.
Proxy port	If you are creating a proxy connection, enter the port used for the HTTP or HTTPS connection.
Username	Enter the user name for the connection towards the other JMap Server. This name must have a corresponding user account.
Password	Enter the password to connect to the other JMap Server.

Advanced Parameters	
Number of connections	Enter the initial size of the connections pool to determine the number of connections towards the other JMap Server that will remain open.

Maximum connections	Enter the maximum number of connections allowed for this pool. The number entered must be equal to or above the initial number of connections. If the pool's size must be increased, new connections will automatically be created until the maximum value is reached. The maximum value may be deactivated in order to increase the size of the pool, if needed.
Connection timeout	The connection inactivity timeout is used to close and reopen connections that are inactive for a long period. This mechanism ensures that the remote JMap server does not close inactive connections. Make sure that this value is lesser than the connection timeout of your JMap server. A default value of 2 hours is appropriate most of the time.
Connection wait timeout	The maximum wait time when opening a network connection to a remote JMap server. This parameter is used to prevent deadlocks in situations where the remote JMap server is not responding.

### Reinitializing connections

When reinitializing a pool of connections to JMap Server, all open connections will be closed and new ones will be created. This action may be useful to force reconnection to a JMap Server.

### Deleting connections

Deleting a connection to JMap Server deletes this connection's entire configuration.

### Connection statuses

Each connection has a status. This status indicates the condition of the connection towards JMap Server. The following table describes the possible statuses of a connection.

Status	
CONNECTED	Connections to JMap Server were successfully created and are ready to be used.
ERROR	Connections to JMap Server are broken. The connection cannot be used until the error has been resolved and the connections have been reopened. Resetting the connection may resolve this issue. You can view a description of the error by clicking on the word Error displayed in red.


## Permissions for the remote connection

This section has two tabs: **Permissions** and **Owners**. The owners are the only ones who can manage the administrative permissions for the connection, manage the list of owners and delete it.

Permissions	
Administrate remote connection	This permission allows you to modify the connection and manage user permissions on the connection. It doesn't allow you to remove the connection or to manage administrative permissions.
Access remote connection	Lets you see the detailed information of the connection and allows you to use the connection, without being able to modify it.

## Configuring JMap Server to JMap Server connections

When you click on the name of a connection, the **Remote connection configuration** interface displays.



- 1 General information about the connection.

- 2 Remote connection pool configured when the connection was created.
- 3 Information about the connection and the remote server, configured when the connection was created.
- 4 References. This section lists the spatial data sources that use this connection. Clicking on their name will take you to their configuration page.
- 5 Buttons to edit, [reinitialize](#), [deactivate](#) or [delete](#) the connection.
- 6 This menu allows you to access the [Permissions](#) section of the remote connection.

## Deactivating a remote connection

You can deactivate a remote connection without removing the connection configuration. The local server can no longer query the remote server. Deactivating a connection is useful when the remote server stops responding and causes delays in the local server.

## Spatial Data Sources

A spatial data source in JMap, as its name implies, is any source that can provide spatial data. Spatial data sources are separated into 2 families : **vector** data sources and **raster** data sources. Vector data sources provide vector spatial data along with its attributes, and raster data sources provide raster data (images). Configuring data sources is usually the first step to publishing spatial data with JMap.

Some spatial data sources work with a file reader to load spatial data from files in various formats (e.g. mif files, shape files, tiff image files, etc.). Other data sources access the data stored on remote spatial data servers (e.g. PostGIS, Oracle Spatial/Locator, ArcSDE, WMS/WFS servers, etc.).

Once a spatial data source is created, it must be updated before it can be used. Updating a spatial data source means preparing it for use by JMap Server. In concrete terms, this operation involves different tasks, depending on the type of data source. Generally speaking, for data sources that access data stored in files, the contents are read by JMap Server and inserted in the tables of JMap's System database. A spatial index is then built for fast access, and attribute statistics are calculated. For data sources that access data stored on spatial data servers like Oracle Spatial/Locator or WFS systems, the update process is simpler and only involves calculating attribute statistics. Updating file data sources takes more time than updating server data sources.

Spatial data sources are listed in the Spatial data section in JMap Admin. The table displayed presents basic information about each data source. When you click on the name of a data source, a details section is displayed. This section presents some useful information about the spatial data source and provides some management functions associated with it.

### Basic concepts

#### Editable data sources

Some spatial data sources support data editing (writing) by JMap. This is the case of most DBMS type data sources (PostGIS, Oracle Spatial, etc.). In this manual, each section pertaining to a specific type of data source indicates whether it supports reading only or reading and writing.

File type data sources (SHP, GML, etc.) do not support data editing. However, there is an option allowing you to transform this type of data source into a **JMap Spatial** data source, which will then allow you to edit spatial and descriptive data in JMap. Once this transformation has been done, the data source will no longer be linked to the original files. All data modifications will have to be performed directly using JMap's editing tools.

#### Including multiple files


In most data sources that read files, multiple files can be integrated together to form continuous maps. It is frequent for CAD users to split a territory in rectangular tiles. By reading all tile files together, JMap administrators can recreate continuous maps, provided that the files contain the same data structure (geometry, layers and attribute types).



## File browsing

JMap Admin provides a file browser that allows you to navigate through the file system of the server where JMap Server is running in order to select the files to include in the data sources. Local and network storage units can be used, as long as the JMap Server process has access to them.

You can also create user paths. These paths are shortcuts that allow you to save time when browsing the system. They can also be used to write paths that are specific to an operating system, such as Windows UNC (e.g. \\myserver\data). To create a user path, you must go to the root of the file system and click on **Add user path...**



*File browser with user path*

To restrict browsing in the file system, you can define one or more root folders. The JMap administrator will not be able to navigate outside these folders. To do this, you must add a line to the file **jmapserver.properties**.

```
admin.filebrowser.roots=c:/data/DataGeo|Data;d:/data2|Data2
```

In this example, two root folders are created, named Data and Data2.

## Uploading files

Accessible through the file browser, the **Uploads** directory contains files uploaded by all users directly to JMap Server from JMap Admin. If you want to upload a file for use as a spatial data source, click on this folder to access the upload interface.

Enter a name for the file and press **Upload**. The file will be uploaded to a directory created automatically for your user account. The file is accessible to all user accounts.

## Updating spatial data sources

Before a spatial data source can be used to create layers, it must be updated. In JMap, updating a data source generally involves collecting information on the spatial data and its attributes and preparing data for fast and efficient access. This process may be very brief or may take several minutes, depending on the type of data source and amount of data.

In JMap Admin, you can update a data source by clicking on **Update** in its information section. You can also update several data sources simultaneously by selecting them in the section displaying the list of data sources and clicking on **Update**.

## Scheduling automatic data source updates

You can schedule automatic updates for spatial data sources. This action may be helpful if you use data sources that read data files. If the files are frequently modified, you can schedule automatic updates that will occur on a regular basis (every day at midnight, for instance) for the appropriate data sources. Each data source can have its own schedule.

In order to schedule updates for a given data source, click on **Schedule** from that data source's details section or in the list of data sources. Afterwards, simply follow the wizard to define the specific moments when the updates will take place. Scheduling options are very flexible.

Once these tasks have been scheduled, you can view the current schedule for a data source by viewing its information section.

At any time, you can access the list of all planned updates for data sources by clicking on **Scheduler** in the JMap Server section.

## Deleting spatial data sources

You can delete spatial data sources by clicking on **Delete** from the data source's information section. You can also delete data sources by selecting them in the section listing the sources and then clicking **Delete**. When a data source has been deleted, its entire configuration is permanently deleted. The data itself (the file or database) is not affected.

## Statuses of spatial data sources

Each spatial data source has a status. The status indicates the condition of the data source, i.e. if it is ready to be used, if an error occurred, etc. The status of a newly created data source is always

set to **not ready** (unless you checked the auto-update flag). This means that the data source cannot be used yet. In order to be used, every data source must be updated at least once.

Data sources can be updated in batches. A maximum of 3 data sources can be updated simultaneously. Other data sources to be updated are queued until they can be updated.

The following table describes the possible statuses of a spatial data source:

Statuses	
Error	An error occurred. The data source cannot handle requests. See error message to determine the source of the error.
Job queued	The data source is waiting to be updated. A maximum of 3 data sources can be updated simultaneously. The data source can still handle requests if it was updated at least once before.
Update needed	The configuration of the data source has been modified and it must be updated before the changes are effective. The data source can still handle requests.
Not ready	The data source is not ready to handle requests. This status is typically attributed to a data source that has just been created but has not yet been updated.
Ready	The data source is ready to handle requests.
Updating	The data source is being updated. Depending on the type of data source and volume of data, the update process can be very fast or it can take a certain amount of time. The data source can still handle requests if it was updated at least once before.

## System spatial data sources

*System* spatial data sources are data sources that are automatically created by JMap to support JMap data source and layer sharing. Normally, these resources do not need to be managed and they are not displayed by default in the list of spatial data sources. If you wish to display them, you can select **Show system data sources** in the display settings of the list of spatial data sources.

## Creating Spatial Data Sources

To begin creating a new spatial data source, go to the **Spatial data** section and click on **Create**. Certain parameters are common to all data sources, while others are specific to each type of data source.

Identification	
Name	Enter a name for the new spatial data source. The name must be unique.
Type	Select the type of data source that matches the type of the data to read. All supported data source types are shown in the list. You can also search the list by typing a few letters in the search field.
Description	Optionally enter a description for the new spatial data source. This description can only be viewed by the JMap administrator.

Note that custom data source types may also exist. These are new types of data sources that are developed for special purposes using the JMap SDK.

The next configuration steps will depend on the data source type you selected. For more information on configuring a specific type of spatial data source, refer to the appropriate section in this manual.

## Projections

The projection of the data source must be selected to match the projection of the data. If this parameter is not set correctly, the data displayed may be invalid.

Projections	
Original projection	The projection or spatial coordinate system of the data in the data source.

**Note:** At the last stage of creating a spatial data source, the **Start update automatically** option allows you to initiate the update when you click on **Finish**. If you do not select this option, you will have to launch the update manually from the spatial data section in order for your changes to be taken into account.

## Configuring Spatial Data Sources

The spatial data source (SDS) configuration interface allows you to access information on a source as well as parameter configuration functions such as metadata, permissions, and attributes.

The screenshot shows the 'Data source configuration' window in JMap 7. The interface includes a top navigation bar with 'Edit', 'Update', and 'Delete' buttons (6) and a menu icon (7). The main content area is divided into five sections:

- General information (1):** Fields for Name (Arbres), Id (155), Description, Status (Ready), and Editable (Yes).
- Parameters (2):** Fields for Data source type (JMap Spatial Table), Database (System), Geometry table (arbres), Key attribute (JMAP\_ID), Id field (JMAP\_ID), Geometry field (JMAP\_GEOMETRY), Spatial index table (JMAP\_EDIT\_INDEX\_155), and Projection (Longitude/Latitude (WGS 84) - EPSG:4326).
- Spatial index information (3):** Fields for Last update (Mar 23 2018 2:00 PM), Update time (0.925 second), Elements (212), and Extent (X: -74.35, Y: 4.60, Width: 77.94, Height: 42.24).
- Attributes (4):** A table listing attributes with columns: Name, Title, Type, SQL type, Indexed, and Relationships. Attributes include JMAP\_ID, AUTHOR, CREATION\_TIME, MODIFICATION\_TIME, ESPECE, DIAMETRE, MALADIE, INTERVENTION, DATE\_OBS, HAUTEUR, ID\_SUB\_SPECIE, SPECIES\_FR, SPECIES\_EN, SPECIES\_ES, SUB\_SPECIES\_FR, SUB\_SPECIES\_EN, and SUB\_SPECIES\_ES.
- References (5):** A tree view showing projects, with 'Montreal (EPSG:3857)' listed under 'Projects'.

*Spatial data source configuration interface*


- 1 General information configured when creating the SDS.
- 2 SDS parameters configured when it was created. The hyperlink allows you to access the DB that contains the data.
- 3 Spatial information. The extent corresponds to the geographical extent of the elements contained in the SDS. When it has no elements, the values are equal to 0.
- 4 Attributes. This section presents a list of SDS attributes. Clicking on the [name](#) of an attribute will open a window, allowing you to configure its properties.
- 5 References. This section lists the projects and layers that use this SDS.
- 6 These buttons allow you to edit, update or delete the SDS configuration.
- 7 The menu provides access to the [Metadata](#), [Permissions](#) and [Schedule](#) sections.

## Attributes

The attribute configuration window contains two tabs: **Metadata** and **Attribute sample**. This button



is used to update the statistics of the SDS.

Metadata	
Type	Indicates the attribute's data type.
SQL Type	Indicates the SQL type of the attribute data.
Indexed	Check this box to have the attribute indexed.
Title	You can change the title of the attribute. This icon  allows you to provide the title in multiple languages.
Format pattern	Specify a format pattern for displaying SDS items. The pattern must follow the Java standards. This article offers more details: <a href="https://docs.oracle.com/javase/tutorial/i18n/format/decimalFormat.html">https://docs.oracle.com/javase/tutorial/i18n/format/decimalFormat.html</a> .
Upon saving, recursively apply to associated layers...	By checking the appropriate boxes, you will apply the title and/or format pattern of the attribute to all layers that are associated with the SDS.

The **Attribute sample** tab displays the value of the attribute for a sample of SDS elements.

## Vector Data Sources

Vector data sources are used to access vector spatial data (points, lines, polygons, etc.). See the following sections for information on the various types of vector data sources that are supported.

[JMap ADF / E00 Arc / Info reader](#)

[JMap KML reader](#)

[JMap Spatial Table](#)

[JMap CSV reader](#)

[JMap MID / MIF reader](#)

[MySQL Spatial](#)

[JMap DGN V7 / V8 File reader](#)

[JMap SHP reader](#)

[Oracle Spatial / Locator](#)

[JMap DWG / DXF reader](#)

[JMap TAB reader](#)

[Personal geodatabase \(ESRI\)](#)

[JMap EDIGEO reader](#)

[Annotations in a database](#)

[PostGIS](#)

[JMap File geodatabase \(ESRI\) reader](#)

[ArcGIS REST](#)

[SQL Server Spatial](#)

[JMap GeoJSON reader](#)[ArcSDE geotadabase \(ESRI\)](#)[WFS Server](#)[JMap GML reader](#)[Coordinates in a database](#)[WKB or WKT in a database](#)[JMap GPX reader](#)[Enterprise geodatabase \(ESRI\)](#)[JMap IFC reader](#)[JMap Server](#)

## Attributes

When configuring a vector spatial data source, you need to configure attributes for the data source. All available attributes are listed in a table. By default, all attributes are included but some attributes can be excluded, in which case they will be completely ignored by JMap Server. It is also possible to specify for which attributes JMap Server should create an index in order to optimize performances when queries are performed on these attributes (if no index is used, this will not affect map download and display times). These indexes are used when performing attribute queries on these fields.

This section also contains settings to configure external attributes. See [External Attributes](#) for more details on this topic.

Attributes	
Key attribute	A key attribute is used when JMap must establish relationships between certain data and your spatial data. It is important to choose an attribute whose values will never change. If you do not need this parameter, you can keep the default value.
Include	Included attributes are processed by JMap Server. They can be used in reports, to produce thematic maps, for labeling, etc. Excluded attributes are totally ignored by JMap Server. By default, all available attributes are included.
Indexed	JMap Server can create an index on an attribute to speed up queries that will use this attribute. If you plan to use an attribute for attribute queries, this attribute should be indexed, especially if the data source has a lot of elements.

## JMap ADF / E00 Arc / Info reader

Read	Yes
Write	No

JMap Server can read ADF and E00 files as a spatial data source. These files are normally produced by ESRI's Arc/Info software.

Parameters	
Selected files	Select one or more ADF or E00 files to be read. If you select several files, they must all share the same attributes list.
Layers	Select one or more layers to be included in the data source. The data on other layers will not be read.

## JMap CSV reader

Read	Yes
Write	No

JMap Server can read CSV files or any text file with separated values that contain x and y coordinates. These coordinates can be used for layers of points. The first row must contain the field names. The allowed separators are commas (,), semicolons (;) and tab characters. Text fields may or may not be inside double quotes. X and Y coordinates must be numeric values.

Parameters	
Selected files	Select one or more CSV files to read. If selecting more than one file, all files must have the same list of attributes.
Separator	Select the separator used in the files to read.
Data type	Select the appropriate data type for each field.
X field	Select the field that contains the X values. Only numeric fields are listed.



Y field	Select the field that contains the Y values. Only numeric fields are listed.
---------	--

## JMap DGN V7 / V8 File reader

Read	Yes
Write	No

JMap Server can read DGN version 7 and 8 files as a spatial data source. Select the data source type that is appropriate for your DGN files' version. DGN files are generally produced by Bentley MicroStation.

DGN files are often paired with a database of attributes. This can be an MS Access database or any other database system. If the DGN files have attributes stored in a separate database, you must first configure a database connection pool for that database before proceeding. See [Creating Databases](#) for more information on database connection configuration.

Parameters	
Selected files	Select one or more DGN files to read. If selecting more than one file, all files must have the same list of attributes and geometries must be of the same type.
Convert polygons to lines	Check this option if you want polygons to be read as lines.
Attribute database	Optionally, select the database that contains the attributes. This database must be already configured in JMap Admin.
Layers	Select one or more layers to include in the data source. Data on other layers will not be read.

## JMap DWG / DXF reader

Read	Yes
Write	No

JMap Server can read DWG and DXF files produced by Autodesk Autocad versions 12 to 2018 as a spatial data source. Block attributes are read and converted into element attributes.

Parameters	
Selected files	Select one or more DWG or DXF files to read. If selecting more than one file, all files must have the same list of attributes and geometries must be of the same type.
Source	The Autocad file contains a model space and a paper space. The paper space contains additional elements that are intended for printing. Select the space to use in order for the data to be read by JMap (typically the model space).
Line and polygon options	<p><b>No conversion:</b> No conversion will be done.</p> <p><b>Convert closed lines to polygons:</b> Closed line objects will be read as polygons by JMap.</p> <p><b>Convert polygons to lines:</b> Polygon objects will be read as lines by JMap.</p>
Block reference options	<p><b>No conversion:</b> No conversion will be done. The different types of objects (lines, polygons, ...) will be treated separately by JMap.</p> <p><b>Convert block references to complex elements:</b> The different types of objects (lines, polygons, ...) that compose the blocks will be read together and treated as complex elements by JMap.</p> <p><b>Convert block references to points:</b> JMap will replace block references by points. This has the effect of considerably reducing the size of the data when the blocks are composed of many objects.</p>
Layers	Select one or more layers to include in the data source. Data on other layers will not be read.

## JMap EDIGEO reader

Read	Yes
Write	No

JMap Server can read EDIGEO files as spatial data sources.

Parameters	
Selected files	Select one or more EDIGEO files to be read. If you select several files, they must all share the same attributes list.
Layers	Select one or more layers to be included in the data source. The data on other layers will not be read.

### JMap File geodatabase (ESRI) reader

Read	Yes
Write	No

JMap Server can read ESRI File geodatabases as a spatial data source.

Parameters	
Selected files	Select the directory containing the geodatabase's structure.
Layers	Select one or more layers to be included in the data source. The data on other layers will not be read.

### JMap GeoJSON reader

Read	Yes
Write	No

JMap Server can read GeoJSON files as a spatial data source.

Parameters	
Selected files	Select one or more GeoJSON files to be read. If you select several files, they must all share the same attributes list.

Layers	Select one or more layers to be included in the data source. The data on other layers will not be read.
--------	---

### JMap GML reader

Read	Yes
Write	No

JMap Server can read GML files as a spatial data source. GML files must be paired with schema files (.XSD). If a GML file contains instances of more than one feature type, only one of those types can be chosen as the base type for the data source. JMap can read GML files of versions 2.x and 3.x.

Parameters	
Selected files	Select a GML file to read.
Feature type	Select the feature type to read. GML files must be accompanied by a schema file (XSD).
GML version	Indicate the version of the GML file (2.x or 3.x).

### JMap GPX reader

Read	Yes
Write	No

GPX is an XML-based GPS data exchange format. JMap Server can read GPX files as a spatial data source.

Parameters
------------

Selected files	Select one or more GPX files to be read. If you select several files, they must all share the same attributes list.
Layers	Select one or more layers to be included in the data source. The data on other layers will not be read.

### JMap IFC reader

Read	Yes
Write	No

JMap Server can read Industry Foundation Classes (IFC) files as a spatial data source. IFC is the standard exchange format commonly used by software for building information modeling (BIM).

### JMap KML reader

Read	Yes
Write	No

JMap Server can read KML files as spatial data sources.

Parameters	
Selected files	Select one or more KML files to be read. If you select several files, they must all share the same attributes list.
Layers	Select one or more layers to be included in the data source. The data on other layers will not be read.

## JMap MID / MIF reader

Read	Yes
Write	No

JMap Server can read MID/MIF files as a spatial data source. These files are generally produced by MapInfo applications.

Parameters	
Selected files	Select one or more MIF files to read. If selecting more than one file, all files must have the same list of attributes, and geometries must be of the same type. Also, each MIF file must be accompanied by a MID file.

## JMap SHP reader

Read	Yes
Write	No

JMap Server can read shape files as a spatial data source. They are generally produced by ESRI applications.

Parameters	
Selected files	Select one or more shape files to read. If selecting more than one file, all files must have the same list of attributes, and geometries must be of the same type. Also, each shape file (SHP) must be accompanied by a DBF file and an SHX file.
DBF charset	Select the character set used for the attributes stored in the DBF file. If this parameter is not set correctly, some characters may not be properly displayed. The default value is CP437, which is correct most of the time.

## JMap TAB reader

Read	Yes
Write	No

JMap Server can read TAB files as spatial data sources. These files are usually produced with MapInfo applications.

Parameters	
Selected files	Select one or more TAB files to read. If you select several files, they must all have the same attributes list, and the geometries must be of the same type.
Layers	Select one or more layers to be included in the data source. Data on other layers will not be read.

## Annotations in a database

Read	Yes
Write	No

JMap has its own storage format for annotations in database tables. If you have any annotations in this format, JMap Server can use them as a spatial data source. Annotation tables in JMap format have a certain number of required fields, as explained in the table below. An SQL query must be provided. The query will be executed to read the data and it can access more than one table at a time.

The database connection must already be configured. Refer to the [Creating Databases](#) section for more details on this topic.

Parameters	
Database	Select the database from which the data must be read. This database must already be configured in JMap Admin.
SQL query	Enter the SQL query used to extract annotations from the database.

Geometry table	Select the physical table containing the geometries. By clicking on Load, you will obtain the list of fields returned by the query. This action is necessary to configure the remaining parameters.
X field	Select the field containing the X coordinate of the lower left position of the text.
Y field	Select the field containing the Y coordinate of the lower left position of the text.
Id field	Select a field containing unique identifiers. Only fields containing whole numbers are listed.
Text field	Select the field containing the annotation text.
Height field	Select the field containing the height of the annotation, indicated in data units.
Angle field	Select the field containing the rotation angle of the annotation text. The angle is indicated in degrees and increases clockwise. The zero value indicates that the text is horizontal.

## ArcGIS REST

Read	Yes
Write	No

JMap Server can connect to ArcGIS Server and ArcGIS Online REST services to access vector data published by this type of service. Geometries and attributes are available, but the other information (styles, scales...) is ignored and must be configured in the layers of the JMap project.

Note that it is also possible to create a JMap project by importing an existing layer configuration from an ArcGIS REST service. Refer to [Creating projects](#) for more information.

Parameters	
URL	URL of the service of an ArcGIS REST layer. e.g. <a href="http://sampleserver1.arcgisonline.com/ArcGIS/rest/services/Demographics/ESRI_Census_USA/MapServer/5">http://sampleserver1.arcgisonline.com/ArcGIS/rest/services/Demographics/ESRI_Census_USA/MapServer/5</a>



Username	Enter the username to authenticate and log in to the ArcGIS REST service.
Password	Enter the password to authenticate and log in to the ArcGIS REST service.

### ArcSDE geodatabase (ESRI ArcGIS 10.0 and earlier)

Read	Yes
Write	Yes

JMap Server can read Enterprise geodatabases that use the ArcSDE service (ArcGIS version 10.1 and earlier) to extract spatial and attribute data to be used as a spatial data source. The connection to the ArcSDE service must already be configured. See [Creating Databases](#) for more information.

Parameters	
SDE Connection	Select the SDE connection to use to extract spatial data and attributes. The connection uses the ArcSDE driver and must already be configured in JMap Admin.
Layer	Select the feature class to read. Each table in the SDE database is associated with a different feature class.
Id field	Select the field that contains unique identifiers. Only integer fields are listed. The field is usually called OBJECT_ID.
Creation time field	This parameter is optional. If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.  This field is used to manage transaction conflicts and must be present in the attributes of editable layers for the feature to be enabled.

Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.
Metadata database	(Optional) This field is used to define the database containing the value domains and the relationships to be used. <a href="#">These must have been exported from ArcSDE beforehand in a specific table structure.</a>

There is a special attribute configuration option that is available only with ArcSDE data sources that have attribute domains.

Attributes	
Data source	Select whether the attribute values should be used directly (Attribute) or if they should be substituted by the values specified in the domain (Domain).

## Exporting ArcSDE domains

In order for JMap to use ArcSDE attribute domains, they must be exported into database tables that JMap can understand. There is a tool that plugs into ArcCatalog to create such tables. Please contact K2 Geospatial for more information on this.

## Coordinates in a database

Read	Yes
Write	Yes

JMap Server can connect to any relational database to extract X and Y coordinates that can be used as a spatial data source to create layers of points. The database must contain at least coordinate fields (numeric values) and a field with unique integer values to be used as element identifiers. An SQL query must be provided. This query will be executed to read the data and it can access one or many tables at the same time.

The connection to the database must already be configured. See [Creating Databases](#) for more information.

Parameters	
Database	Select the database to read the data from. It must already be configured in JMap Admin.
SQL query	Enter the SQL query used to extract coordinates and attributes from the database.
Geometry table	Select the physical table that effectively contains the x and y coordinate values. Pressing <b>Load</b> will retrieve the list of fields returned by the query. This action is necessary to configure the rest of the parameters.
X field	Select the field that contains the X values. Only numeric fields are listed.
Y field	Select the field that contains the Y values. Only numeric fields are listed.
Id field	Select a field that contains unique identifiers. Only integer fields are listed.
Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

### Enterprise geodatabase (ESRI ArcGIS 10.1 and later)

Read	Yes
Write	Yes

JMap Server can read Enterprise geodatabases from ESRI (ArcGIS 10.0 and later) to extract spatial and attribute data to be used as a spatial data source. The connection to the database must already be configured. See [Creating Databases](#) for more information.

The spatial data source supports value domains. Relationships defined in the enterprise geodatabase (EGDB) are also supported, but can only be exploited by using external tools.

The data source attributes will correspond to the table columns. To associate the data from other tables, a view can be created in the database and then be configured as a layer in JMap. The data source attributes will then correspond to the columns returned by the view.

<b>Parameters</b>	
Database	Select the database connection to be used to extract the spatial data and attributes. The connection is a standard database (Oracle, SQL Server, etc.). It must already be configured in JMap Admin.
System tables schema	Select the database schema where the metadata tables are located.
Schema	Select the database schema in which the table (or view) containing the feature class will be read.
Layer	Select the feature class to be read. Each table in the database corresponds to a different layer.
Id field	Select a field that contains unique identifiers. Only integer fields are listed. The field is usually called OBJECT_ID.
Geometry field	Select the field that contains the geometries.
Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.  This field is used to manage transaction conflicts. It must be present in the attributes of editable layers in order for the feature to be enabled.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

## JMap Server

Read	Yes
Write	Yes

JMap Server may use a vector spatial data source that comes from another JMap Server instance. To enable this, you must start by configuring a connection towards the other JMap Server. Refer to [JMap Server to JMap Server Connections](#) for more information.

Parameters	
Remote connection	Select the connection towards another JMap Server instance that must be used to extract spatial data and attributes. The connection must already be configured in JMap Admin.
Data source	Select the existing vector spatial data source on the other JMap Server instance you wish to access. This data source must be shared by the other server.

## MySQL Spatial

Read	Yes
Write	Yes

JMap Server can connect to MySQL Spatial databases to extract spatial data and attributes to be used as a spatial data source. The only special requirement is the presence of a numeric column with unique integer values to use as element identifiers. An SQL query must be provided. This query will be executed to read the data and it can access one or many tables at the same time.

The connection to the database must be already configured. See [Creating Databases](#) for more information on this topic.

Parameters	
Database	Select the MySQL database to read the data from. It must already be configured in JMap Admin.

SQL query	Enter the SQL query used to extract geometries and attributes from the database.
Geometry table	Select the physical table that contains the geometries. Pressing <b>Load</b> will retrieve the list of fields returned by the query. This action is necessary to configure the rest of the parameters.
Geometry field	Select the field that contains the geometries.
Id field	Select a field that contains unique identifiers. Only integer fields are listed.
Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

## JMap Spatial Table



Read	Yes
Write	Yes

JMap Spatial is the format used to store JMap's spatial and descriptive data. It is based on the WKB format ([http://en.wikipedia.org/wiki/Well-known\\_binary](http://en.wikipedia.org/wiki/Well-known_binary)).

An existing JMap Spatial table may be used as a spatial data source or a new one can be created to receive data.

Parameter	
Table	Select the JMap Spatial table to be used as a data source. If the table does not exist, you can create it by clicking on Add table.

### Adding or modifying a table

Click on **Add table** to create a new table in JMap Spatial format. You can also select an existing table and click on **Edit table** to change its name or structure. When creating or editing a table, you can add new fields to the table in the **User Attributes** tab by clicking on  and remove fields by clicking on . Note that there are other fields in the table displayed on the **System Attributes** tab. These include geometry fields (vary according to geometry type), spatial index fields, and so on. These fields are created and populated automatically by JMap.

Once the table has been created or modified, it can be used for the spatial data source.

### Oracle Spatial / Locator

Read	Yes
Write	Yes

JMap Server can connect to Oracle Spatial or Locator databases to extract spatial data and attributes to be used as a spatial data source. The only special requirement is the presence of a numeric column with unique integer values to be used as element identifiers. An SQL query must be provided. This query will be executed to read the data and it can access one or many tables at the same time.

The connection to the database must already be configured. See [Creating Databases](#) for more information.

Parameters	
Database	Select the Oracle database to read the data from. It must already be configured in JMap Admin.
SQL query	Enter the SQL query used to extract geometries and attributes from the database.
Geometry table	Select the physical table that effectively contains the geometries. Pressing <b>Load</b> will retrieve the list of fields returned by the query. This action is necessary to configure the rest of the parameters.
Geometry field	Select the field that contains the geometries.
Id field	Select a field that contains unique identifiers. Only integer fields are listed.

Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

## Personal geodatabase (ESRI)

Read	Yes
Write	No

JMap Server can read ESRI Personal geodatabases to extract spatial and attribute data to be used as a spatial data source. This format uses Microsoft Access files to store the data. The connection to the Access database must already be configured using the MS Access driver. See [Creating Databases](#) for more information on this topic.

Parameters	
Database	Select the database to read the data from. This database must connect to an MS Access file. It must already be configured in JMap Admin.
SQL query	Enter the SQL query used to extract geometries and attributes from the database.
Geometry table	Select the physical table that effectively contains the geometries. Pressing Load will retrieve the list of fields returned by the query. This is necessary for the rest of the configuration.
Id field	Select a field that contains unique identifiers. Only integer fields are listed. The field is usually called OBJECT_ID.



## PostGIS

Read	Yes
Write	Yes

JMap Server can connect to PostGIS databases to extract spatial data and attributes that can be used as a spatial data source. The only special requirement is the presence of a numeric column with unique integer values to be used as element identifiers. An SQL query must be provided. This query will be executed to read the data and it can access one or many tables at the same time.

The connection to the database must be already configured. See [Creating Databases](#) for more information.

Parameters	
Database	Select the PostGIS database to read the data from. It must already be configured in JMap Admin.
SQL query	Enter the SQL query used to extract geometries and attributes from the database.
Geometry table	Select the physical table that effectively contains the geometries. Pressing <b>Load</b> will retrieve the list of fields returned by the query. This is necessary for the rest of the configuration.
Geometry field	Select the field that contains the geometries.
Id field	Select a field that contains unique identifiers. Only integer fields are listed.
Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

## SQL Server Spatial

Read	Yes
Write	Yes

JMap Server can connect to Microsoft SQLServer Spatial databases to extract spatial data and attributes that can be used as a spatial data source. The only special requirement is the presence of a numeric column with unique integer values to be used as element identifiers. An SQL query must be provided. This query will be executed to read the data and it can access one or many tables at the same time.

The connection to the database must be already configured. See [Creating Databases](#) for more information.

Parameters	
Database	Select the SQLServer Spatial database to read the data from. It must be already configured in JMap Admin.
SQL query	Enter the SQL query used to extract geometries and attributes from the database.
Geometry table	Select the physical table that effectively contains the geometries. Pressing <b>Load</b> will retrieve the list of fields returned by the query. This is necessary for the rest of the configuration.
Geometry field	Select the field that contains the geometries.
Id field	Select a field that contains unique identifiers. Only integer fields are listed.
Automatically convert to valid geometry	<p>When this option is active, the geometries will automatically be converted using the SQL MakeValid function. Note that the result can therefore differ from the original geometry, as the function will alter invalid geometries.</p> <p>This option also requires a valid SRID, so a projection must be specified for the data source. MakeValid is not supported by all SQL Server versions, please consult SQL Server's help to confirm the compatibility of the function for the geometries or geographies and your particular SQL Server version. Activating this option without meeting these criteria will result in an error during the insertion or updating of the data.</p>
Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data

	can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

Note: The projection system selected for the spatial data source must exactly match the spatial reference identifier (SRID, e.g. EPSG) of the elements of the table, for the elements to be displayed.

## WFS Server

Read	Yes
Write	No

Web Feature Service (WFS) is a standard proposed by the [Open Geospatial Consortium](#) that defines how client applications should request map vector data and attributes from a WFS compatible server. The protocol used is HTTP and the data returned is typically in Geography Markup Language (GML). WFS servers publish their capabilities in an XML document that specifies the types of requests supported and provides a description of available features.

JMap Server can read data from WFS servers versions 1.0.0 and 1.1.0 to be used as a spatial data source.

Parameters	
URL	Enter the GetCapabilities URL that will return the capabilities of the WFS server. It should be similar to:  <pre>http://www.server.com/wfs? SERVICE=WFS&amp;VERSION=1.0.0&amp;REQUEST=GetCapabilitie</pre>
Feature types	The list of feature types is returned by the WFS server after pressing Load. Select one feature type to read.

## WKB or WKT in a database

Read	Yes
Write	Yes

JMap Server can connect to databases containing geometries that have been coded according to WKB and WKT standards ([http://en.wikipedia.org/wiki/Well-known\\_text](http://en.wikipedia.org/wiki/Well-known_text)).

In addition to the column containing the geometry, you must have a number column with unique integer values used as element identifiers. There must also be 4 columns containing the values of minimum bounding rectangles (MBR).

An SQL query must be provided. The query will be launched to read the data and it can access more than one table at a time.

The connection to the database must already be configured. Refer to the section [Creating Databases](#) for more information on this topic.

Parameters	
Database	Select the database from which the data must be read. This database must already be configured in JMap Admin.
SQL query	Enter the SQL query used to extract geometries and attributes from the database.
Geometry table	Select the physical table containing the geometries. Clicking on Load displays the list of fields returned by the query. This action is required to proceed with the configuration.
Geometry field	Select the field containing the geometries.
Geometry type	Select the format of the data to read, either WKB or WKT.
Encoding (for WKB only)	If the data format is WKB, you must indicate the type of coding used by the data: Little Endian or Big Endian.
MBR X1	Minimum X value of the minimum bounding rectangle (MBR) in the geometry.
MBR Y1	Minimum Y value of the minimum bounding rectangle (MBR) in the geometry.
MBR X2	Maximum X value of the minimum bounding rectangle (MBR) in the geometry.

MBR Y2	Maximum Y value of the minimum bounding rectangle (MBR) in the geometry.
Id field	Select a field that contains unique identifiers. Only the fields containing whole numbers are listed.
Creation time field	(Optional) If you want this data source to be editable by JMap, this field will show the creation date of each object. If no field is selected, the data can still be edited, but this information will not be maintained.
Modification date field	(Optional) If you want this data source to be editable by JMap, this field will contain the date each object was last modified. If no field is selected, the data can still be edited, but this information will not be maintained.
Author field	(Optional) If you want this data source to be editable by JMap, this field will either contain the name of the user who created each object or the name of the user who made the last change. If no field is selected, the data can still be edited, but this information will not be maintained.

## Raster Data Sources

Raster data sources are used to access raster spatial data (images). See the following sections for information on the various types of raster data sources that are supported.

[ECW / JPG2000](#)

[JMap Server](#)

[GDAL \(Geospatial Data Abstraction Library\)](#)

[OpenStreetMap \(OSM\)](#)

[TIFF / GEOTIFF](#)

[WMS Server](#)

[ArcGIS REST](#)

[WMTS Server](#)

### ECW / JPG2000

With this type of data source, it is possible to read ECW or JPG2000 image files or to connect to an ECWP server ([ERDAS Image Web Server](#)) to obtain images. It is not possible to configure both at the same time.

Parameters	
Selected files	Select one or more ECW or JPG2000 image files to read. If many files are selected, they will be considered as a mosaic. The files must be georeferenced.

**Note:** This type of data can also be read by the GDAL data source with the same performance. This data source is kept for compatibility with existing configurations.

## GDAL (Geospatial Data Abstraction Library)

This type of spatial data source allows you to read a wide variety of raster data formats. [GDAL](#) (Geospatial Data Abstraction Library) is an open source library specializing in raster data conversion and processing.

There can be one or more source image files (mosaic of images). The images of the mosaic can overlap and there can be holes in the mosaic.

When the data source is updated, if the option is activated, a pyramid of lower resolution images is created by JMap Server and stored in the image cache. The image cache is then used for high performance production of images on the fly at specific resolutions. Depending on the initial image sizes and parameters, the image cache size can become voluminous. Typically, the total image cache is about the same size as the original images. Available disk space must be sufficient before updating this data source. It is possible that the data format selected will not require the creation of a pyramid. In this case, the parameter will be ignored.

Parameters	
Selected files	Select one or more image files to read. If many files are selected, they will be considered as a mosaic. The files must be georeferenced.
Cache path	The directory where JMap Server will store generated image files for the various resolutions. Default is JMAP_HOME/cache/raster.
Image interpolation	Method for producing images with reduced resolutions from images with higher resolutions. Default is "Cubic" and this method usually produces the best results.
Compute statistics (may take some time)	Statistics on image pixels simplify the analysis of these images. JMap extensions such as <a href="#">Imagery</a> use these statistics to work. Calculating statistics can take several minutes and this option should only be

	activated when necessary. If you do not need statistics, do not enable this option.
Create a pyramid	Activates the creation of an image pyramid with several resolutions. This greatly improves performance for producing images on the fly.
Pyramid image interpolation	Method used to produce pyramid images. The default value is "Cubic" and this method usually produces the best results.

## TIFF / GEOTIFF

This type of spatial data source can read georeferenced TIFF image files. JMap supports two types of georeferenced tiff images: tiff files with tfw files (the tfw files contain georeferenced data) or geotiff files (georeferenced data inside image file).

There can be one or more source image files (mosaic of images). The images of the mosaic can overlap and there can be holes in the mosaic. When the data source is updated, lower resolution images are created by JMap Server and stored in the image cache (pyramid of images). The image cache is then used to produce images on the fly at specific resolutions with optimal performance. Depending on the initial image sizes and parameters, the image cache can become voluminous. Typically, the space used by the cache is the same size as the original images. Available disk space must be sufficient before updating this data source.

Note: This type of data can also be read by the GDAL data source with the same performance. This data source is kept for compatibility with existing configurations.

Parameters	
Selected files	Select one or more image files to read. If several files are selected, they will be considered as a mosaic. The files must be georeferenced.

The other parameters don't need to be modified most of the time.

Reader options	
Cache path	The directory where JMap Server will store generated image files for the various resolutions. Default is JMAP_HOME/cache/raster.
Interpolation type	Method for producing images with reduced resolutions from images with higher resolutions. Default is bicubic and usually gives the best results.

Compression type	Type of compression of the lower resolution images in cache. Default is none and offers the best performances but uses more disk space.
------------------	---

Resolutions	
Resolutions	Number of lower resolution images to prepare and resolution ratio in relation to the higher resolution images. Default is 8 with each image resolution divided by 2. All these resolutions form the pyramid of images.

## ArcGIS REST

JMap Server can connect to ArcGIS Server and ArcGIS Online REST services to access WMTS-type raster data published by this type of service.

Parameters	
URL	URL of the service of an ArcGIS REST layer. e.g. <a href="http://sampleserver1.arcgisonline.com/ArcGIS/rest/services/Demographics/ESRI_Census_USA/MapServer/5">http://sampleserver1.arcgisonline.com/ArcGIS/rest/services/Demographics/ESRI_Census_USA/MapServer/5</a>
Username	Enter the username to authenticate and log in to the ArcGIS REST service.
Password	Enter the password to authenticate and log in to the ArcGIS REST service.

## JMap Server

JMap Server can use a raster spatial data source that comes from another JMap Server instance. To enable this, you must start by configuring a connection towards the other JMap Server. Refer to [JMap Server to JMap Server Connections](#) for more information.

Parameters
------------



Remote connection	Select the connection towards another JMap Server instance that must be used to extract spatial data and attributes. The connection must already be configured in JMap Admin.
Data source	Select the existing raster spatial data source on the other JMap Server instance you wish to access. The data source must be shared by the other server.

## OpenStreetMap (OSM)

JMap Server can use the OpenStreetMap map as a raster data source. No parameters need to be configured for this type of data source.

## WMS server

Web Map Service (WMS) is a standard proposed by the [Open Geospatial Consortium](#) that defines how client applications must request maps from a WMS compatible server. The protocol used is HTTP and the maps returned are typically images in popular formats (PNG, GIF, JPEG, etc.). WMS servers publish their capabilities in an XML document that specifies the types of requests supported as well as the metadata (list of layers, supported projections, etc.).

By configuring WMS data sources, you allow JMap to connect to and query WMS compatible servers (versions 1.0 to 1.3). You can then create raster layers based on these WMS data sources inside projects.

Parameters	
Get server capabilities (GetCapabilities)	Enter the GetCapabilities URL that will return the WMS server's capabilities. The URL should look like this:  <pre>http://www.server.com/wms? SERVICE=WMS&amp;VERSION=1.3.0&amp;REQUEST=GetCapabilities</pre>
Enable HTTP authentication	Enable this option if the WMS server controls access to the WMS service via HTTP authentication. In this case, enter the username and password that must be used.

Once you have obtained the capabilities, you can define the parameters for the other types of requests in the WMS protocol. JMap Admin automatically suggests default queries that usually work very well. They are generated from the GetCapabilities request. If you wish to modify these default requests, you must select the **Override default request** option and enter new requests.

For each type of request, you can also activate HTTP authentication and provide sign-on parameters.

Parameters	
Get map(GetMap)	This request is used to get a WMS server map.
Get feature info(GetFeatureInfo)	This request is used to get the attributes of a map element.

## WMTS Server


Web Map Tile Service (WMTS) is a standard offered by the [Open Geospatial Consortium](#) that determines how client applications perform queries to obtain map data in the form of predefined tiles from a data server.

By configuring WMTS data sources, you enable JMap to connect to and query WMTS-compatible servers (version 1.0.0). You can then create raster layers based on WMTS data sources within projects.

Parameters	
URL	<p>Enter the GetCapabilities URL that will return the capabilities of the WMTS server. The URL should be similar to this one:</p> <p><code>http://www.server.com/wmts?SERVICE=WMTS&amp;VERSION=1.0.0&amp;REQUEST=GetCapabilities</code></p> <p>Examples</p> <p><a href="https://basemap.nationalmap.gov/arcgis/rest/services/USGSHydroCached/MapServer/WMTS/1.0.0/WMTSCapabilities.xml">https://basemap.nationalmap.gov/arcgis/rest/services/USGSHydroCached/MapServer/WMTS/1.0.0/WMTSCapabilities.xml</a></p> <p><a href="http://cite.deegree.org/deegree-webservices-3.4-RC3/services/wmts100?service=WMTS&amp;request=GetCapabilities">http://cite.deegree.org/deegree-webservices-3.4-RC3/services/wmts100?service=WMTS&amp;request=GetCapabilities</a></p> <p>Press <b>Next</b> to continue configuring the data source.</p>
Original projection	Select the projection of the map data.
Start update automatically	Check this box to automatically update this data source.

## Spatial Data Source Permissions

In the details section of a spatial data source, click on **Permissions** to access the permissions section. You can also modify permissions in batches. To do this, select several data sources in the list and click on **Permissions**.

A list of authorized users and groups displays. Click on  to add new users or groups. The available users and groups are configured in the JMap Server section of JMap Admin. Refer to the [Managing Users and Groups](#) section for more information on managing users in JMap.

Only administrator permissions are associated with spatial data sources.


Permissions for spatial data source	
Remote access	Allows a user to access this spatial data source through a JMap Server to JMap Server connection. This permission must be granted to the user account through which the secure connection between both JMap Servers was established. For more information on this topic, refer to sections <a href="#">JMap Server to JMap Server Connections</a> and <a href="#">Sharing Spatial Data Sources</a> .
Administrate spatial data source	Allows an administrator to modify the configuration of the spatial data source.
Access spatial data source	Allows an administrator to create layers that take their data from this data source.

## Sharing Spatial Data Sources

Spatial data sources can be shared in order to be accessed by other JMap Server instances. This way, data can be stored in a single location but is accessible from several JMap Server instances.

In JMap Admin, you can share a spatial data source by granting the **Remote access** permission to one or more users on this spatial data source. This choice must be consistent with the user who established the connection from the JMap Server that must access the shared spatial data sources.

Refer to sections [Spatial Data Source Permissions](#) and [JMap Server to JMap Server Connections](#) for more information on this topic.

Once a spatial data source has been shared, a  icon displays in the list of data sources, in the **Shared** column.

## External Attributes

External attributes for a spatial data source are attributes that are obtained from an external database (external means a database that is separate from the data source itself). The external attributes are added to the list of existing attributes and can thereafter be used like any other attribute in reports, queries, mouseover, thematics, etc.

External attributes are available only for vector spatial data sources that read data from files (shp, mif, tab, dwg, dgn, etc.) and JMap Spatial tables. When working with vector data sources that access data inside existing spatial databases (PostGIS, MySQL Spatial, Oracle Spatial/Locator, etc.), this option is not available. In that case however, it is often easy to include all needed attributes using normal SQL joins with other tables or by creating views.

External attributes are created from the spatial data source creation wizard.

To create an external attribute, choose **External attributes** in the Attribute section of the wizard. Press **Add** and choose one of the following two methods: **Select fields** or **SQL query**.

### Select fields

Choose this option in order to select one or more fields from a specific database table from which you want to obtain the values. This option is the simplest method, and it allows you to create several attributes at once.

Settings	
Database	Select the database from which the attribute values will be taken. This database must already be configured in JMap Admin.
Schema	Select the schema containing the table.
Table	Select the table containing the fields to be used as external attributes.
Include	The list of available fields is displayed. Select the ones to be included as external attributes.
GET VALUE FROM	Indicate the name of the field.
ATTRIBUTE NAME	You can give the external attribute a name that will be different from the field name.
DYNAMIC ATTRIBUTE	Select this option if you want the attribute to be dynamic. Dynamic attributes are read directly from the source in a dynamic manner. Attributes that are not dynamic are imported into JMap's system database and are only reread when the data source is updated.  In certain cases, dynamic attributes can reduce the system's performance.

Join on fields	Select the parameters of the join between the external data and the JMap data source.
Aggregation type	<p>This option is only available if a single field is selected. Select the aggregation method to use if more than one value is found for the same geometry:</p> <p><b>Keep first element:</b> Keep only the first value found.</p> <p><b>Average:</b> Calculate the average value to use as the attribute value. Only available for numeric attributes.</p> <p><b>Summation:</b> Calculate the summation value to use as the attribute value. Only available for numeric attributes.</p> <p><b>Using separator:</b> Build a string containing all values separated by the specified character. Only available for text attributes.</p>

### SQL query

Choose this option to provide an SQL query that will extract the attribute values in the database. This method is more flexible, but limits you to creating one attribute at a time.

Parameters	
Attribute name	Enter a name for the external attribute.
Dynamic attribute	<p>Select this option to make the attribute dynamic. Dynamic attributes are read directly from the source in a dynamic manner. Non dynamic attributes are imported in JMap's System database and are only reread when the spatial data source is updated in JMap Admin.</p> <p>Dynamic attributes can impact performances in some situations.</p>
Database	Select the database from which the attribute values will be taken. This database must already be configured in JMap Admin.
SQL query	Enter the SQL query to be executed in the external database that returns the values to use for the external attribute, along with the field used to join with the data source. Press Execute to test the query and to initialize the other parts of the interface.
Get value from	Select the table and the field to get the values from. Only those returned by the SQL query are available.
Join on fields	Select the parameters of the join between the external data and the JMap data source.

Aggregation type	<p>Select the aggregation method to use if more than one value is found for the same geometry:</p> <p><b>Keep first element:</b> Keep only the first value found.</p> <p><b>Average:</b> Calculate the average value to use as the attribute value. Only available for numeric attributes.</p> <p><b>Summation:</b> Calculate the summation value to use as the attribute value. Only available for numeric attributes.</p> <p><b>Using separator:</b> Build a string containing all values separated by the specified character. Only available for text attributes.</p>
------------------	---

## Metadata

---

### Metadata of a Data Source

Metadata can be associated with spatial data sources in JMap. It can include information such as the person who produced the data, the date it was updated, a description, etc. Users can view this information for the corresponding layers in JMap applications. Metadata can be entered directly into JMap Admin using preset templates or it can be taken from an external metadata management system. Refer to the [Metadata Templates](#) section for more information on creating templates.

To access the metadata settings of a spatial data source, click on **Metadata** in the details section of a spatial data source. The following options are available:

Metadata	
Type	<p>3 options are possible:</p> <p><b>None:</b> No metadata is associated with this data source.</p> <p><b>External:</b> The metadata comes from a metadata management system that is outside of JMap and accessed through a URL. The URL must be entered in the URL field below.</p> <p><b>Template:</b> The metadata is entered directly in this section using the selected template.</p>
URL	<p>If the type of metadata is external, this setting defines the URL to be opened in order to view the metadata associated with this spatial data source.</p>

Template	If the type of metadata is template, select the template to be used for this data source. The metadata entry form for this template displays. Enter the metadata in the various fields.
----------	---

Layers whose data originates from spatial data sources with metadata will automatically inherit this metadata. Metadata can be viewed by users of JMap Web and JMap Pro applications.

## Metadata templates





JMap allows you to define metadata templates to document spatial data sources directly in JMap Admin. Once the template has been defined, you can associate it to certain data sources and enter all the information, which users can then easily view in JMap's applications. If you already use a metadata management system that can be accessed in a browser, you can also create a direct link between certain layers and this system.

You can create as many metadata templates as you want.

The metadata template management section can be accessed by clicking on **Metadata templates** in the **Spatial data** section.

### Creating a metadata template

Click on **Create** to create a new template. The interface shows the following options.

Metadata template	
Name	Enter a name for this template. Template names must be unique.
Default language	Among the languages available for the metadata template, choose the default language that will be used when the requested language is unavailable or when translations are missing.
Available languages	Select one or more languages that will be supported for this metadata template. All text elements in the template's configuration (section and field names, field values) will have to be translated into each supported language. You must select at least one language.
Section name	You can define one or more metadata sections. Enter a name for the current section. Click on  to add a new section. Click on  to delete a section.
Label	Enter a label for the field. The label text will be displayed in the metadata entry window and in the consultation interface.  Click on  to add a new field. Click on  to delete a field.

Type	<p>Select the type of field. The following types are available:</p> <p><b>TEXT:</b> Alphanumeric data entry field on a single line.</p> <p><b>TEXTAREA:</b> Data entry field spanning multiple lines to allow for longer text.</p>
Mouseover	<p>By selecting this option, the field value will be displayed in the mouseover bubble when a layer is pointed in the layer bar of JMap applications. This bubble presents a summary of a layer's metadata.</p>



## Projects

In JMap, map data is organized in projects. A project is composed of an ordered list of layers. Typically, when a JMap application connects to JMap Server, the application opens a project and displays the project layers. You can create as many projects as you want.

Each layer of a project is associated with a spatial data source. The data source provides the data of the layer. Different projects can contain layers sharing the same data sources, allowing different data bindings, styles, etc. for the same data. Also, more than one layer in a project can share the same data source. This is useful when using layer filters to show different data of the same data source on multiple layers.

A project is a secured resource, which means that permissions are associated with it in order to control access by users. This allows precise control of which users or groups will be allowed to open each project. Similar access control is also available for each layer in the project.

The screenshot shows the 'Project Configuration' interface for a project named 'Montreal (EPSG:3857)'. The interface is divided into three main sections: 'General information', 'Project settings', and 'Initial view settings'. The 'General information' section includes fields for Name, Id, Description, Default language, and Available languages. The 'Project settings' section includes fields for Map projection, Map unit, Distance unit, Display unit, and Extent. The 'Initial view settings' section includes a field for Minimum scale. On the right side, there is a 'Preview' section showing a map of Montreal and a 'Layers' section with a 'STATUS' label.

General information	
Name	Montreal (EPSG:3857)
Id	5
Description	
Default language	French
Available languages	French English Spanish

Project settings			
Map projection	WGS 84 / Pseudo-Mercator - EPSG:3857		
Map unit	Meters		
Distance unit	Meters		
Display unit	Meters		
Extent	X	Y	
	Width	Height	
	-20,039,512.09	-20,039,512.09	
	40,079,024.19	40,079,024.19	

Initial view settings	
Minimum scale	1: Infinity

*Interface for configuring JMap projects*

## Creating Projects

To create a new project, press **Create** in the section listing the projects. Projects are created by walking through a wizard.

Identification	
Name	Enter a name for the new project. The name must be unique.
Description	Optionally enter a description for the new project. Used for administrative purposes.
Default language	Among the languages available, select the one that will be used by default when the requested language is unavailable or when translations are missing. For more information, refer to the <a href="#">Multilingual Projects</a> section.
Available languages	Select one or more languages that will be supported by the project. All text elements in the project's configuration (name of project, names of layers, mouseover bubbles, etc.) will have to be translated into each supported language. At least one language must be selected. For more information, refer to the <a href="#">Multilingual Projects</a> section.
Usage statistics	Select this option if you wish to obtain usage statistics regarding this project, the layers it contains, and the public contexts that are created in the JMap Pro applications deployed from this project.

Parameters	
Map projection	Determines how the data will be displayed in the client applications. Any data that is in a different projection will be converted on the fly to this projection. Note that changing the map projection of a project invalidates the layer cache. This can temporarily reduce the performance of applications.
Map unit	The map unit is automatically selected according to the selected map projection.
Display unit	The unit used to display map coordinates.
Measurement	<b>Geodetic:</b> Distance and area measurements will be made using spherical calculations based on the projection's ellipsoid. <b>Cartesian using:</b> Distance and area measurements will be made from calculations on the two-dimensional plane using the specified projection.
Distance unit	The unit used to display distances (measurements, zoom levels, etc.).
Minimum scale	The minimum scale of the map. Users cannot zoom out further when this limit is reached.

Maximum scale	The maximum scale of the map. Users cannot zoom in further when this limit is reached.
Background color	Default color to use for the background of the map.
Default selection color	Color of selected objects on the map. It can also be defined for each layer.

## Project source

When creating a project, you can either create a new empty project or import an existing project configuration from another source. When you use an existing configuration, you can automate the creation of the project's layers and avoid reconfiguring everything in JMap Admin. Currently, only one option is available for importing a project configuration: importing projects from an ESRI ArcGIS REST Service.

### Importing ArcGIS REST projects

You can choose to import the layer configuration from an ESRI ArcGIS REST service. JMap will import the project's parameters, the layers and their symbology, the scale parameters, the extents, etc.

Select the **ArcGIS REST** option and click on **Next**.

ArcGIS REST	
URL	Enter the URL of the ArcGIS Server REST service (e.g. <a href="http://sampleserver1.arcgisonline.com/ArcGIS/rest/services">http://sampleserver1.arcgisonline.com/ArcGIS/rest/services</a> ). Afterwards, click on <b>Load</b> to show the list of available layers.
Username	Enter the username to authenticate and log in to the ArcGIS REST service.
Password	Enter the password to authenticate and log in to the ArcGIS REST service.
Layers	Select the layers whose configurations you wish to import. JMap creates a layer in the project for each imported layer. The configuration of the JMap layer is similar to that of the original layer, but there may be some differences.

JMap supports the import of OGC WMTS raster layers.


In the REST service layer import interface, icons indicate layers whose format is not compatible with JMap.


## Configuring Projects

The configuration interface of a project allows you to access information on the project. This interface also contains functions to configure various parameters, such as the initial view of the project in the applications.

The screenshot shows the 'Project Configuration' window for 'Montreal (EPSG:3857)'. It features a top navigation bar with 'Edit' and 'Delete' buttons. The main content is divided into four numbered sections: 1. General information (Name: Montreal (EPSG:3857), Id: 2, Description, Default language: French, Available languages: French, English, Spanish); 2. Project settings (Map projection: WGS 84 / Pseudo-Mercator - EPSG:3857, Map unit: Meters, Distance unit: Meters, Display unit: Degrees, Extent: X: -20,039,512.09, Y: -58,115,529.83, Width: 40,079,024.18, Height: 796,263,032.23); 3. Initial view settings (Minimum scale: 1: infinity, Maximum scale: 1: 1,000, Initial view coordinates: X1: -8,218,853.54, Y1: 5,685,905.21, X2: -8,218,853.54, Y2: 5,716,327.14, X3: -8,171,615.45, Y3: 5,716,327.14, X4: -8,171,615.45, Y4: 5,685,905.21, Background color: white, Default selection color: cyan); 4. References (Deployed applications). A Preview map (5) shows the project area with various layers (6) listed on the right, including Buildings, Airport territory, Manoeuvring area, Public utilities UPIM, Plan and profile PPIM, Sewer EGIM, Aqueduct (inventory) IEIM (IE), Aqueduct (atlas) AEIM (PE), Underground power lines, Track lights, Tracks, Fire hydrants - Dorval, and Noise Exposure Contour.


*Project configuration interface*

- 1 General information configured when creating the project.
- 2 The project's parameters. They are configured when the project is created. The project's extent corresponds to the extent of the layers that make up the project. When the project does not have any layers, the values are equal to 0.
- 3 Initial view settings. These parameters are specified when the project is created. The initial view is defined by clicking on  in the **Preview** section. By default, the initial view corresponds to the extent of the project. When the project does not have any layers, the values are equal to 0.
- 4 **References.** This section indicates the deployed applications that use this project.




- 5 **Preview.** This section displays when the project contains at least one layer. It shows a map preview, and you can zoom in or out on it. Click on  to open a [JMap Web Preview](#) in a separate window or a [JMap Pro Preview](#) in which you can define the initial view and test the project configurations.
- 6 **Layers.** This section shows a list of the project layers and their statuses. Shortcuts allow you to access the interfaces to add and organize layers.
- 7 These buttons allow you to edit or delete the project configuration.
- 8 The menu allows you to access the [Layers](#), [Queries](#), [Permissions](#) and [Image producer](#) sections.

## JMap Web Preview

The **JMap Web Preview** opens a JMap Web application in a new browser window.




The preview offers all the functionality of JMap Web applications and allows you to validate the project's configuration. It also allows you to configure the initial view of the project when it is opened


in JMap Web applications. To do this, click on  and then on  **Initial extent**. A rectangle displays to delimit the initial extent. Click on  **Maximum extent** to display the maximum extent. When you close the preview, the geographic coordinates of the initial extent are automatically saved.

## JMap Pro Preview

The **JMap Pro Preview** opens a JMap Pro application offering all the functionality of JMap Pro applications. You can validate the project configuration.



*JMap Pro preview*

You can also delimit the initial view of the project, when it is opened in JMap Pro applications. Click on . A rectangle displays to delimit the initial view. When you close the preview, the geographic coordinates of the initial view are automatically saved.

## Image producer

The image producer of a JMap project is used to produce images on demand for that project. These images are used for JMap Web and JMap Mobile applications. When a user works in JMap Pro, the image producer is not used because the data is transferred in vector format (except for photos).

Normally, the image producer's settings do not need to be modified because the default configuration is adequate. The following table describes the settings of the image producer.

Memory settings	
Maximum size	The maximum amount of memory allotted to the project's image producer. This memory is used to store the project's vector data in order to accelerate the production of images. For very large projects, this setting can be increased.
Memory release	Determines the percentage of memory to be released when the memory of the image producer is saturated.
Thread pool settings	
Initial size	The number of threads determines the number of images that can be produced simultaneously.
Maximum size	If the number of threads increases due to high demand, this value limits the number of threads.
View wait timeout	The maximum period before an image request expires. This option is usually disabled.

**Note:** With previous versions of JMap (before 7.0), the image producer needed to be reset after changes were made in the project. This is no longer necessary with JMap 7.

## Managing Projects

The Projects section in JMap Admin displays a list of existing projects. From this section, projects can be created, cloned or deleted.

### Modifying an existing project

A project can be modified by pressing Edit from the project detail section. Modifying a project goes through the same steps as when the project was created. If the projection of the project is changed, the vector data cache of the layers is cleared.


## Cloning projects

You can clone an existing project by selecting it from the table and pressing Clone. All layers inside the project are copied to the new project. Note that the underlying spatial data sources and databases are not copied. Instead, they are shared between the layers of the new project and the layers of the old project.

## Deleting projects

You can delete an existing project by selecting it in the table and clicking on Delete. You can also delete a project from its configuration section. Deleting a project permanently deletes all layer configurations included in it. The spatial data sources are not affected.

## Project Permissions

From the project detail section, press Permissions to access the project permissions section. A list of currently allowed users and groups is displayed. Press  to add new users or groups and automatically grant them the Open this project permission. The available users and groups are configured in the JMap Server section in JMap Admin. See [Managing User Accounts and Groups](#) for more information about managing users in JMap.

Project permissions are divided into two categories: administrator permissions and user permissions.

### Administrator permissions

Administrator project permissions define the project administration rights for the users authorized to use JMap Admin. For more information on concepts related to permissions and administration roles in JMap Admin, refer to the [Managing Permissions](#) section.

Permissions	
Administrate project	Allows an administrator to modify the project and its content.
Access project	Allows an administrator to access a project to view its content and to use it when deploying JMap applications.

### User permissions

User project permissions determine which users and groups can open a project. Access will be denied to users who do not have the appropriate permissions. Security can also be configured at the layer level. For more information on this topic, refer to the [Layer Permissions](#) section.



Permissions	
Open this project	Allows a user to open a project from a JMap application.

### Anonymous user

Adding the anonymous user to the list of users authorized to open the project gives users the possibility to open a project without any authentication. This is equivalent to removing all security for opening the project. This is useful for public applications, when no project access control is needed.

### Everyone user

Adding the everyone user to the list of users authorized to open the project allows any authenticated user to open a project. This is useful for private applications where all users are allowed to open a project but must authenticate themselves.


## Multilingual Projects


JMap projects can be configured to support several languages. This way, each user can view the project in his or her own language, as long as the language is available and the translations have been provided. When a JMap application is launched, it can automatically identify the language of the user's operating system and use this language for the project and graphical interfaces. This behavior depends on the options selected when deploying the application.

For a project supporting multiple languages, each text element that is visible to the users can be translated into each language. For example, you can provide translations for the project name, the names of the layers, labels, mouseover bubbles, forms, etc.

To enable multilingual support, you must choose at least 2 languages when creating or editing a project. You must also select the default language.

Languages	
Available languages	Select the languages that will be available for the project. At least one language must be selected.
Default language	Choose the default language among those that are available. When you enter text in the various configuration sections of the project and layers, you must enter it in the default language.  If the user's language is not supported for the project or if translations are missing, JMap will automatically use the default language.

Afterwards, you can enter the translations in the sections identified with the  symbol when configuring the project and layers.



*Translation interface for a project supporting 3 languages*

If translations are not provided in all available languages for certain text elements, the text will automatically be displayed in the default language.

## Organizing Layers


There are two aspects to organizing layers in a project. One is to define the order of appearance of the layers on the map. Layers at lower positions are drawn first and layers at higher positions are drawn at the end. Top layers can hide elements of bottom layers. The other aspect is to create a logical hierarchy based on the nature of the layers. In other words, this allows the creation of groups (and subgroups) of layers that have a logical relationship. For example, there could be a

group of layers related to roads, another to hydrography, and another to census. Organizing them in groups makes it easier for the users to work with layers.


To start organizing the layers, open the **Layers** section of the project.

## Ordering layers

To order layers of a project, open the tab titled **List**. This section presents the layers in their order of appearance on the map. The lowest position is the first layer to be drawn on the map. To change the order, you must use the **Modify** menu located at the top of the column displaying the position of each layer. You can also select one or more layers and move them using the available options (Move up, Move down, Move at..., etc.). In addition, you can open a window displaying all the layers and reorder them using drag-and-drop actions.



*The MODIFY menu offers several options to modify the order of the layers.*



The Reorder layers... option allows you to reorder layers using drag-and-drop actions.

## Grouping layers

To organize layers in groups, open the tab named Hierarchy. This section presents the current hierarchy of layers. By default, all layers of the project are in one unique group called **Layers**. To create a new group, press **Create group**. Fill the layer group parameters as described below:

Layer group	
Name	Enter a name for the new group. The name must be unique.
Description	Optionally enter a description for the new group. This description will be visible to users.
Visible	Makes the group initially visible when the project is opened. All visible layers inside the group will be displayed.
Always listed	Ensures the group is always listed (displayed in the layer management window ) even if it contains no layer. By default, empty groups are not listed. A group can be empty if it contains no layer, if all the layers it


contains are not listed or if the user doesn't have the permission to see the layers of the group.

Once groups have been created, you can move layers towards these groups using the **Modify** menu located at the top of the column displaying the position of each layer.

The screenshot shows the JMap Admin interface for 'Layers for project The World'. The 'Hierarchy' tab is selected, showing a tree view with 'Layers' expanded to 'Hydrography'. A table lists layers with columns for ORDER, NAME, PUBLISHED, VISIBLE, and LISTED. A 'Modify' menu is open over the first layer, offering options to move it within the group or towards other groups.

	ORDER	NAME	PUBLISHED	VISIBLE	LISTED
<input type="checkbox"/>	Modify				
<input type="checkbox"/>	6	Hydrography	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	7	Countries	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

*The MODIFY menu offers several options to move a layer within a group or towards another group of layers.*



*The Move to... option allows you to move a layer towards another group.*

## Attribute Queries

Attribute queries are used to find and select elements of a map layer using their attribute values or a database associated with the layer. In JMap Admin, JMap administrators create the queries and their associated forms. Then, users of JMap applications use those forms to enter attribute values to search for. All elements whose attribute values match the values entered are then selected or listed in an elements explorer.

You can access the query configuration section by clicking on **Queries** in the **Projects** section.

### Creating a new attribute query

To create a new query, press the **Create** query button in the Attribute queries section. This will open the query configuration interface. Parameters will vary depending on the type of query selected.

Query	
Title	Enter a title for the query. Users will see this title in a list of queries.
Layer	Select the layer on which the query will be executed. A search field is provided to simplify layer selection.
Maximum scale	Specify the maximum scale used to present the results on the map. This is used to avoid zooming in too closely on the results.

Max. returned values	Specify the maximum number of elements this query can return. The query will refuse to execute if the return size is higher than this limit. This is used to avoid very long queries that could slow down the system.
Query templates	<p><b>Basic:</b> With this type of query, the search is only performed on the layer attributes. This is the simplest type of query.</p> <p><b>External database:</b> With this type of query, the search is performed in an external database that has a field linking to an attribute of the layer. Setting up this type of query is more complex but offers more searching flexibility.</p>

## Layer queries

Layer queries	
WHERE	<p>WHERE clause of the SQL query used to run the search. Here is where all the search criteria will be defined. Typically, this clause contains numbered parameters (\$param1, \$param2, etc.) that will be replaced by the values the user enters in the form.</p> <p><b>Examples:</b></p> <p>COUNTRY='\$param1'</p> <p>Selects the layer elements for which the attribute value COUNTRY is equal to the value entered by the user. The attribute value must perfectly match the value entered (\$param1).</p> <p>lower(COUNTRY) like lower('\$param1%')</p> <p>Selects the layer elements for which the attribute value COUNTRY is similar to the value entered by the user. The attribute value must begin with the value entered (\$param1). Since the lower operator is used, the search is not case sensitive.</p> <p>POP2000&gt;=\$param1 and POP2000&lt;\$param2</p> <p>Selects layer elements that have the POP2000 attribute value within the range defined by the two values that were entered (\$param1 and \$param2).</p>
Form layout	Press this button to configure the query form. See <a href="#">Forms</a> for more information.



## External queries

This type of query is used when the search must be conducted within the data of an external database. The external database must contain a field that links to a layer attribute. A select SQL query is executed in the external database and the values returned are then associated with the layer elements using the link field.

External queries	
Database	Select the database in which you would like to perform your query.
SQL query	<p>Enter the SQL query that will be executed in the database to search for elements.</p> <p><b>Example:</b></p> <pre>select * from cities where CITY_LANGUAGE='\$param1'</pre> <p>Searches the database selected above, in the cities table. Retrieves all fields of records for which the value of the CITY_LANGUAGE field is equal to the value entered by the user (\$param1).</p>
Layer attribute	Among the layer attributes, indicate which one is used to link with the database.
Field	Among the fields returned by the SQL query, indicate which one is used to link with the layer.
Form layout	Click on this button to configure the query form. Refer to the <a href="#">Forms</a> section for more information on this topic.

## Required and optional parameters

Although search forms are designed to mark fields as required or optional, the where clause of the query must be adjusted to support this option. To accomplish this, any part of the query that is associated with optional parameters must be included between braces ( { } ).

Example of where clause:

```
CITY = '$param1' and { COUNTRY = '$param2' }
```

This example searches for cities for which the attribute value CITY is equal to the value of parameter 1 (\$param1) entered by the user and who optionally have their value for the COUNTRY attribute equal to the value of parameter 2 (\$param2) entered by the user. If parameter 2 is left blank, the entire block { COUNTRY = '\$param2' } is removed from the query, along with the and operator, which is now an orphan. Note that the administrator must absolutely define \$param2 as optional when designing the form. Refer to the [Forms](#) section for more information on designing forms.

## Multiple values for the same parameter

Multiple values can be entered with a List (multiple choices) type field in the forms. The values are separated by the delimiter character ; (semicolon). This option can be activated in the WHERE clause of the query. The syntax is as follows:

```
$multiple{true|false} {$delimiter{;}}
```

Example:

```
CITY = '$param1{$multiple{true} $delimiter{;}}'
```

Searches for cities whose CITY attribute value is equal to one of the values entered in parameter 1. The values are separated by semicolons.

## Managing attribute queries


Attribute queries can be modified by administrators. In JMap Dakar and later versions, when a project's queries are modified, the applications that disseminate the project do not need to be redeployed because the changes are reflected directly.

### Deleting attribute queries

Deleting an attribute query permanently deletes the query and its associated form. To delete a query, select it in the list and click on **Delete**.

### Organizing attribute queries

Attribute queries can be organized into groups. This is particularly useful for projects that have a large number of queries.

To create a new group, click on the **Create group** button. To modify the order of groups, click on the **Modify** button and select **Reorder groups**. The window that is displayed allows you to drag and drop the groups in order to change their order. To rename a group, click on . To delete a group, select it in the list and click on **Delete**.


## Style Templates

Style templates are predefined styles that can be reused across many projects and layers. They help save time because a style can be configured once but used at many places. Style templates also help create standardized maps.

Once a style template is configured, it can be used in every place a style is needed (layer styles, selection styles, thematics, etc.). A style template can be used as a **reference** or as a **copy**. When used as a reference, if the style template is modified, all layers that refer to it will also use the modified style. When used as a copy, the style is detached from the style template and can be modified independently thereafter.

Style templates are associated with only one type of map element (point, line, polygon, etc.) and cannot be used for other types of elements.

To use a style template, click on **Use a style template** from any style configuration interface. See [Style](#) for more information.



*Using a style template*

You can access the style template configuration section by clicking on **Style templates** in the **Projects** section.

## Creating style templates

To create a new style template, press **Create**.

Style templates	
Name	Enter a unique name for the style template.
Type	Select the element type associated with the new style template. Depending on the selected type, the style configuration interface will be different.
Description	Optionally enter a description for the style template.

The rest of the configuration depends on the selected element type and is identical to normal style configuration. See [Style](#) for more information. Press **Finish** to complete the creation of the style template.

## Deleting style templates

To delete a style template, select it in the list and press **Delete**.

## Personal Layers

---

Personal layers are layers of data created and populated by users. When creating a new personal layer, the user specifies a name, a geometry type and a set of attributes. The layer configuration and the data (geometries and attributes) are stored in the JMap Server System database. Once they have been created, personal layers can be shared between users with a permission system. They can also be converted to normal layers inserted in a project by the administrator. Users need a special permission granted by the administrator to create personal layers.

You can access the personal layers section by clicking on **Personal layers** from the **Projects** section.

In JMap Admin, the administrator can see a list of existing personal layers. It can be displayed by personal layer or by user. When selecting a personal layer, you can see which users have access to it. When selecting a user, you can see which personal layers the user has access to. You can also click on a personal layer in the list to open its details section.

## Deleting a personal layer

To delete a personal layer, select it in the list and press **Delete**. Be aware that deleting a personal layer also deletes its configuration and all its data. This action cannot be undone.

## Publishing a personal layer

Publishing a personal layer transforms it into a regular project layer. Once it is published, a personal layer can no longer be managed by users. However, it can still be edited if the administrator grants the appropriate permissions to users. To publish a personal layer, select it in the list, press **Publish** and select the project in which the layer will be inserted.

## Layers

A project is composed of an ordered list of layers. Layers are used to display data extracted from spatial data sources. Each layer is related to a specific spatial data source. Vector layers are related to vector data sources and display vector data while raster layers are related to raster data sources. The layer configuration determines the appearance of the data (style of the layer), the visibility thresholds, what information is associated with the spatial data (attributes), etc. Each layer has its own configuration parameters for labelling, reports, thematics, etc.

Layers are created in the project they belong to. Specific permissions can be configured for each layer. Thus, some layers can be accessed only by a subset of users authorized to open the project.

The layers of a project can be organized into a logical tree-like structure or hierarchy. This feature is useful to better organize information when working with projects that have a high number of layers. In client applications, users are able to control the visibility of the layers belonging to the same group in one click. Refer to the section titled [Organizing Layers](#) for more information on this subject.

Layers can be copied from one project to another or even shared between various projects located on the same JMap Server or on separate JMap Servers. Refer to the section titled [Sharing Layers](#) for more information on this topic.

The layers of a project are displayed in the **Layers** section, which may be accessed from the JMap Admin project configuration interface. In the **List** tab, the table shows basic information about each layer of the project. When you click on the name of a layer, a details section displays. The **Hierarchy** tab displays the groups and subgroups with the layers that compose them. The tasks you can perform from this tab are detailed in the [Organizing Layers](#) section.

In the **List** tab of the **Layers** section of a project, you can perform the tasks described in the table. For some tasks, you must select more than one layer.

Layers	
Add - Create	Initiates the creation of a new layer. Refer to <a href="#">Creating Layers</a> .
Add - Clone/Reference	Allows you to duplicate or reference a layer from another project located on the same server or on a different JMap Server. Refer to <a href="#">Sharing Layers</a> .
Add - Import...	Allows you to import layers one by one from a project exported from another JMap server. Refer to <a href="#">Importing layers</a> .
Permissions	Allows you to configure permissions for the selected layers. Refer to <a href="#">Layer Permissions</a> .
Update data sources	Updates the spatial data sources associated with the selected layers. Refer to <a href="#">Spatial Data Sources</a> .

Update caches	Launches the preparation of the vector data cache for the selected layers. Refer to <a href="#">Creating Layers</a> .
Update - Bulk edit...	Allows you to edit certain layer parameters in batches. The <a href="#">Bulk editing a layer set</a> section provides details about this topic.
Delete	Deletes the selected layers.

This button  allows you to access the **Permissions** section, where you can configure the permissions of the selected layers. See [Layer Permissions](#) for more details.

## Importing layers

You can add a layer to a project by importing it from a project that has been exported from another JMap server. The [Exporting and Importing](#) section provides details on exporting and importing a JMap server's resources. To import a layer in a project, you must also create a data source in JMap Server containing the data of the imported layer.

When you select **Add / Import...** the **Importation wizard** will guide you through the process to import one or more layers from the project where they are found.

1. To start the process, select the **Importation file**. Click on **Browse** to access the **File browser**.
2. Select the *.properties* file that contains the project whose layers you wish to import.
3. Click on **Next**.
4. Select the **Project** that contains the layer you wish to import.
5. Select the **Layers** to import.
6. Click on **Next**.
7. If the project in which you are importing the layer contains a layer with the same name as the one you are importing, select an option to resolve the conflict between these layers: **Create a new layer with a different name**, **Replace the existing layer** or **Use existing layer**.
8. Click on **Next**.
9. If the JMap Server in which you are importing the layer contains a spatial data source with the same name as the data source of the layer you are importing, select an option to resolve the conflict between these data sources: **Create a new data source with a different name**, **Replace the existing data source** or **Use existing data source**.
10. Click on **Next**.
11. A summary lists the number of imported resources for the project: layers, databases, remote connections, spatial data sources, style templates, and metadata templates.

- Press **Import**. The layer is added to the project and a new spatial data source is created in JMap Server.

## Bulk editing a layer set

You can edit different settings for a set of layers. You must select the layers to modify in the **List** tab of the **Layers** section of the project. Afterwards, press the **Update** button, and click on the **Bulk edit...** option. The **Bulk edit** interface will open.

Update - Bulk edit...	
Change 'Antialiasing'	Check if you want to change this setting. Check <i>New Value</i> to enable the antialiasing feature. Uncheck <i>New Value</i> to disable the antialiasing feature. The <a href="#">Style</a> section provides details on this parameter.
Change 'Minimum scale'	Check to change the minimum scale for displaying layers. Check <i>Infinity</i> or <i>1:</i> and in this case, indicate the scale. The <a href="#">General Settings</a> section provides details on this topic.
Change 'Maximum scale'	Check to change the maximum scale for displaying layers. Check <i>Zero</i> or <i>1:</i> and in this case, indicate the scale. The <a href="#">General Settings</a> section provides details on this topic.
Change 'Request mode'	Check to change the data request mode. Check the option of your choice. The <a href="#">Creating Layers</a> section provides details on this topic.
Change 'Description'	You can write a new description for the layers.

## Creating Layers

Each layer of a project in JMap takes its data from a spatial data source. Thus, before layers can be created, the related data sources must already exist (see [Creating Spatial Data Sources](#) for more information).

### Creating a new layer

To create a new layer, press **Create** in the **Add** menu of the **Layers** section of a project. Note that the new layer will have the same name as the data source by default. The name can be changed later.

**Spatial data source**

Spatial data source	Select the spatial data source that will provide the data of the layer. Selecting a vector data source will create a vector layer. Selecting a raster data source will create a raster layer.
Name	Enter a name for your new layer. The name must be unique. By default, the layer will take the same name as the selected data source.
Description	(Optional) Enter a description for the new layer. This description will be used for administrative purposes.

The next steps are different for vector layers and raster layers. Note that creating a raster layer is also different for each type of raster data source. Jump to the corresponding section below.

## Creating a vector layer

Geometry type	
Geometry type	If the data source provides more than one type, select the unique geometry type for the layer.

Attributes	
Bound attributes	<p>By default, when layer elements (points, lines, polygons, etc.) are served by JMap Server, the element attributes (or descriptive data) are not. This is because the attributes are not “bound” to the elements. Attribute binding binds attribute data to layer elements. Only bound attributes can be used for the following functions: labeling, mouseover, thematic mapping and displaying attributes in the elements or selection explorer.</p> <p>Select and add the attributes to the list on the right to bind them to the layer. The other attributes will still be available for other functions like attribute queries and information reports.</p> <p>Note that the number of bound attributes has an impact on network and memory usage and thus can reduce the overall performances. Therefore, attributes should only be bound when necessary.</p>

Geometry angle (layers of points only)	
Angle attribute	This section is only available for layers of points. In this section, select a numeric attribute that contains the rotation angles for the symbols



	representing the points of the layer. If you select an attribute of the angle, the symbols will be displayed with a rotation following this attribute value.
Units of angular measure	Choose the rotation unit to apply: degrees or radians
Direction	Choose the rotation direction. Angle values can be interpreted clockwise or counterclockwise.
Origin of rotation	Choose the origin of the rotation to apply: geographic (north) or arithmetic (east).

The request mode determines how the vector data is managed by JMap Server. It can greatly influence the system's overall performance.

Request mode	
Load by tile	<p>The data is requested by rectangular zones (tiles) defined by a predetermined fixed grid that covers all the layer data. Structuring layer data in tiles makes data management more efficient, for network transfers, memory management and cache storage. If the grid is not properly configured, this can have a negative impact on the system's performance or lead to operational problems. When you press the <b>Estimate</b> button, JMap performs a calculation to determine the best configuration for the grid. You can accept these values or modify them according to your needs.</p> <p>This mode offers the best performance because once a tile has been extracted from a data source, it can be cached for a certain amount of time and reused effectively. This is the recommended mode for most applications.</p>
Load by region	<p>The data is requested by random regions, according to the user's navigation actions on the map. Each time the layer needs to be displayed in the application, a new request is sent to JMap Server and the data is extracted again from the spatial data source. This mode is very dynamic as no caching is used, and users can see data changes at every map manipulation (zoom, pan, etc.). Note however that it is much more intensive for JMap Server and, if not used properly, it can affect the system's general performance.</p> <p>This mode must be used for dynamic data. Typically, this data is found in a relational database and can be randomly modified. This is the case for layers that are editable by JMap.</p>

## Advanced parameters

Most of the time, the following advanced parameters don't need to be modified.



Advanced (optional)	
Transformation	<p><b>Apply a translation:</b> Translate each geometry of the layer by X units horizontally and Y units vertically. The original data is not affected.</p> <p><b>Generalize geometries:</b> Generalize (simplify) geometries using the specified tolerance. For a given geometry, all nodes that are closer together than the tolerance are eliminated. In addition, all nodes that are located on the same straight line are eliminated. The original data is not affected.</p> <p><b>Reduce precision (better performance):</b> Use data compression to improve performance. In some rare situations, this option can noticeably reduce data precision. From JMap Dakar, this option is unchecked by default for new layers to avoid performance issues. Layers configured in earlier versions of JMap are not affected.</p>
Caching	<p>This section allows you to define server data caching rules for the vector data and its attributes. The cache is on the server. This improves performances because once data is in the cache, JMap Server does not need to load it again from the data source.</p> <p><b>Activate server data caching for this layer:</b> Use this option to enable or disable data caching on the server for this layer.</p> <p><b>Automatically build the cache when the data source is updated:</b> If caching is enabled, this tells JMap Server to flush and rebuild the cache for this layer, when the corresponding spatial data source gets updated. Building the cache in advance helps to prevent delays for the users. Building the cache may take a long time, depending on the volume of the data.</p> <p><b>Cache timeout:</b> This instructs JMap Server to cache the data no longer than the specified time period. When the timeout is reached, the data is requested again from the data source. This is mostly useful for spatial data sources that get their data from spatial data servers to which JMap Server is connected (Oracle Spatial/Locator, ESRI geodatabases, PostGIS, MySQL Spatial, etc.).</p> <p><b>Update layer cache after I click "Finish":</b> Select this option to have the cache built immediately for this layer. Building the cache may take a long time, depending on the volume of data.</p>
Base Filter	<p><b>SQL conditions:</b> SQL conditions are used to filter the elements of the spatial data source. Only the elements that satisfy the SQL conditions</p>

	will be on the layer. This allows you to create many layers showing different data using the same spatial data source. SQL conditions are interpreted directly by the database system so the syntax is the same as that of an SQL WHERE clause. The where keyword is not necessary.
--	---

## Creating a raster layer based on a WMS data source

To create a raster layer based on a WMS spatial data source, you need to tell JMap what data to request from the WMS server. The WMS server publishes a list of all the layers it can serve and their properties. In JMap, the WMS layer creation interface allows you to select the layers to include in the WMS layer you wish to create.

WMS raster layer	
Connection type (Direct/Server)	<p>The connection type determines if JMap Pro applications will request images directly from the WMS server or if they will send the requests to JMap Server, which in turn will query the WMS server. JMap Web applications are not affected by this setting. If Direct is selected and a JMap Pro application fails to connect to the WMS server, the connection mode will revert to Server.</p> <p>Note that if JMap Server is behind a firewall/proxy, it may need proxy authentication settings in order to access the Internet. See <a href="#">JMap Server Settings</a> for more information.</p>
Output format	The list of output formats offered by the WMS server. You can select the format to use.
Background color	Tells the WMS server what color to use in the background of the map images. Any area where there is no data will be filled with this color.
Use background color as transparent color	Tells the WMS server to use the background color as the transparency color. Using transparency allows the map images to be placed on top of other layers without completely hiding them.
S.R.S.	<p>The list of Spatial Reference Systems offered by the WMS server for the layer. You can select the one to use.</p> <p>Make sure the selected SRS is consistent with the project projection because JMap cannot reproject images received from WMS servers.</p>
Available layers	The list of layers the WMS server is publishing. If you hold your mouse pointer on a layer name, its description will display automatically, along with its attributes. The attributes determine if the layer is Queryable (supports GetFeatureInfo requests), Cascaded (comes from another

	WMS server) or Opaque (not transparent, i.e. the layers found under it will not be visible).
Selected layer(s)	The layers selected among those that are available appear in this list. Click on  to add a new layer to this list. You can select the style to be used. A default style is always provided. Click on  to delete a selected layer.

## Creating a raster layer based on a GDAL, TIFF/GEOTIFF or ECW/ECWP data source.

Raster layer	
Image format	Select the image format to use for image transfers between JMap Server and JMap Pro applications. For air photos, JPEG usually gives the best results.
Image format parameters	Only used with JPEG image format to specify the quality factor (1 means excellent quality and low compression while 0 means low quality and high compression). Test with different values to determine what fits your needs. A value of 0.5 is usually a good compromise. Example: quality=0.6
Background color	Tells JMap Server what color to use in the background of the images. Any area where there is no data will be filled with this color.
Use background color as transparent color	Tells JMap Server to use the background color as the transparency color. Using transparency allows the map images to be used on top of other layers without completely hiding them.

## Creating a raster layer from a WMTS data source

WMTS raster layer	
Layer	Select the layer from the WMTS server that you wish to use to create the layer. Only layers who have the same projection as the project are selectable.
Style	Select the layer style.

## Publishing layers

A layer must be published to be accessible to the users. A layer that is not published is not part of the project, and in no way can users see it or access it.

When a new layer is created, it is not published by default. This allows you to do further configuration tasks on the layer before making it available for the users. For example, it is important to configure visibility thresholds appropriately according to the scale before the layer can be seen by users.

After layer creation, you must press the **Publish** button in the layer's detail section.

Unpublishing an existing layer can be useful to make it unavailable to the users without actually deleting it.

## Configuring Layers

The layer configuration interface allows you to access layer information as well as parameter configuration functions such as style, labels, or reports.

**General information** 1

Name	Bornes incendies
ID	103
Description	
Status	Ready
Published	Yes
Visible	No
Selectable	Yes
Listed	Yes
Overview	No
By reference	No

**Layer parameters** 2

Spatial data source	Bornes incendies
Data source status	Ready
Layer type	Vector
Element type	Point
Request mode	By region
Extent	X: -11,517,718.69 Y: -4,555,452.05
	Width: 27,656,607.05 Height: 10,463,589.54
Offset	X: 2,310,584.83 Y: 676,342.71

**Bound attributes** 3

Name	Title	Type	SQL type	Indexed	Relationships
JMAP_ID	JMAP_ID	Normal	BIGINT	No	
CREATION_TIME	Date de création	Normal	TIMESTAMP	No	
MODIFICATION_TIME	Date de modification	Normal	TIMESTAMP	No	
MODELE	Modèle	Normal	VARCHAR	No	
PRIORITE	Priorité	Normal	VARCHAR	No	
ANNEE_FABR	Année de fabrication	Normal	BIGINT	No	
DATE_INS	Date d'inspection	Normal	DATE	No	

**Visibility thresholds** 4

Minimum scale	1 : infinity
Maximum scale	1 : 0

**Thematics** 5

Name	Type	Enabled

**Labels** 6

Label format	null	aa
Automatic labelling	No	

**Mouseover** 7

Mouseover format	<b>Modèle : </b>EV{MODELE} <b>Date d'inspection : </b>format{DATE_INS, dd/MM/yyyy} <b>Priorité : </b>EV{PRIORITE} <b>Année de fabrication : </b>EV{ANNEE_FABR} photos}
------------------	--



**Reports** 8

Name	Information	Type	Basic
------	-------------	------	-------

**Forms** 9

Name	Bornes incendies	Type	Layer attributes
------	------------------	------	------------------

**Edit** 10 **Delete** 11


- 1 General information configured when creating the layer. This button  provides direct access to the section settings configuration interface.
- 2 Layer parameters configured when it was created. The hyperlink allows you to access the spatial data source that contains the layer data.
- 3 Bound attributes. This section presents a list of attributes related to the layer. Click on the [name of an attribute](#) to open the configuration window of its properties. This button  is used to update the statistics of the attributes.
- 4 Layer visibility thresholds; shows the limits between the minimum and maximum scales for displaying layer elements.
- 5 [Thematics](#). This section presents the layer's thematics. Click on the name of the thematic to access its configuration interface.
- 6 [Labels](#). This section presents information on the labels.
- 7 [Mouseover](#). This section describes the mouseover configured for the layer.
- 8 [Reports](#). This section presents the reports configured for the layer.
- 9 [Forms](#). This section presents information about forms configured for the layer. Click on the form name to access its configuration interface.
- 10 These buttons allow you to edit the layer configuration or delete it.
- 11 The menu provides access to the sections [General](#), [Permissions](#), [Style](#), [Thematics](#), [Labels](#), [Mouseover](#), [Forms](#) and [Reports](#).

The raster layer configuration interface contains the General information, Layer parameters, and Visibility thresholds sections.

## Attributes

The Attribute configuration window contains three tabs: **Metadata**, **Statistics**, and **Attribute sample**.

Metadata	
Type	Indicates the type of data for the attribute.

SQL Type	Indicates the SQL type of the data for the attribute.
Indexed	Check this box to have the attribute indexed.
Title	You can change the title of the attribute. This icon  allows you to provide the title in multiple languages.
Format pattern	Specify a format pattern for displaying SDS items. The pattern must follow Java standards. For more details on this topic, read the following article: <a href="https://docs.oracle.com/javase/tutorial/i18n/format/decimalFormat.html">https://docs.oracle.com/javase/tutorial/i18n/format/decimalFormat.html</a> .

The **Statistics** tab provides simple statistics about the attribute. The **Attribute sample** tab displays the value of the attribute for a sample of layer elements.

## Layer Permissions

There are several different types of permissions for a project's layers. The following tables describe each one of these.


### Administrator permissions

Permissions	
Remote access	Allows a user to access this layer through a JMap Server to JMap Server connection. This permission must be granted to the account of the user who established the secure connection between both JMap Servers. For more information on this topic, refer to the <a href="#">JMap Server to JMap Server Connections</a> section.

### User permissions

Permissions	
View this layer	Allows a user to view a layer in JMap's applications. By default, the everyone user (everyone who has permission to open the project) is authorized to view any new layer. To restrict access to a layer, you must remove this permission from everyone and only add it to the users of your choice.


Add elements	Allows a user to add new elements on the layer and enter attribute values using the form associated with the layer. Editing must be enabled on this layer in order for this permission to be available.
Modify elements	Allows a user to modify the geometries of the elements (move, add/remove nodes, etc.) found on the layer. Also allows the user to modify attribute values using the form associated with the layer. Editing must be enabled on this layer in order for this permission to be available.
Delete elements	Allows a user to delete existing elements on the layer. Editing must be enabled on this layer in order for this permission to be available.
Modify attribute values	Allows a user to open the form of a layer's element attributes and to modify their values. Editing must be enabled on this layer in order for this permission to be available.
Copy / export elements	Allows a JMap Pro user to copy the data of the layer to another layer, or to export the data of the layer using the JMap Exportation extension.

To modify layer permissions, press  in order to select the users and groups to which you wish to grant permissions. Only the users and groups who are already authorized to open the project containing the layer can be granted permissions associated with this layer.

## Sharing Layers

JMap allows you to share layers between projects that are on the same server or that originate from remote servers that are connected. Layer sharing allows you to manage data more effectively (avoids duplication, saves time) by reusing existing layers instead of creating new layers in each project. When the original layers are modified, the changes can automatically be viewed in all projects that have referenced layers pointing towards these shared layers. Referenced layers cannot be modified directly, save a few basic settings. Only the original shared layer can be modified.






*Layer sharing between projects on the same server and on different servers. The properties of the Rivers layer cannot be modified in projects 1 and 3. The original layer is in project 2.*

## Sharing layers between projects on the same JMap Server

To share layers between projects on the same JMap Server, no action is required. Layers can be accessed freely from any project on the same server. Refer to [Accessing shared layers](#) for more information.

## Sharing layers between different JMap Servers

If you wish to share a project's layers in order to access them from another JMap Server, you must assign a special remote access permission to a user for these layers. In order to do this, access the project layers section for which you wish to share these layers.

1. Select one or more layers.
2. Click on **Permissions**.
3. In the permission management interface, select the user account or group to which you wish to assign the remote access permission (you can add user accounts and groups by clicking on )
4. Select the **Remote access** permission. The account used must match the user account through which the connection to this JMap Server was established. If you are using a group, the aforementioned user account must be included within it.

Once the layers have been shared, they can be selected from the remote JMap Server and inserted in this server's projects. Refer to [Accessing shared layers](#) for more information.

To stop layers from being shared, simply remove the **Remote access** permission from these layers.

## Accessing shared layers

To access existing layers from different projects located on the same JMap Server or shared layers on other JMap Servers, you must click on **Add** and select **Clone / Reference** in the layers section of the project to which you would like to add these layers.

In the **Clone / Reference** layers section:

1. Select a JMap Server from which you wish to clone or reference layers. If you choose **Local server**, you can select the projects and layers of the local server without these being shared. The other servers in the list are the JMap Servers for which a JMap Server to JMap Server connection exists. Refer to the [JMap Server to JMap Server Connections](#) section for more information on creating JMap Server to JMap Server connections.
2. Select the project from which you wish to clone or reference layers. Once the project has been selected, the list of available layers displays.
3. Select the layers you wish to clone or reference and move them to the list on the right.
4. Select the **Clone** or **Reference** option.

If you choose the **Clone** option, the selected layers will be duplicated towards your project. They will be exact copies of the original layers, but there will be no connection between the copies and the original layers. You can modify the copies without affecting the originals. If you delete a cloned layer, this doesn't affect the original layer. If you delete the original layer, this doesn't affect its cloned layers. However, duplicated layers always use the same spatial data source as the original layer. If this data source is modified or deleted, this will affect the duplicated layers.

If you select the **Reference** option, the original layers will be accessed by reference. This means that a direct connection will be maintained between the layers of your project and the original layers. You will not be able to modify these layers in your project. If the original layers are modified, the changes will appear wherever references to these layers exist, after a short delay. If you delete a referenced layer, the original layer will not be affected. If you delete the original layer, the referenced layers will no longer work and will have to be deleted manually.

## General Settings

---

The layer general settings section is accessible by clicking on the settings drop-down menu, then selecting General in the layer details section. This section allows you to specify basic layer parameters. These parameters are described below, along with the visibility thresholds.

### General

#### General

Name	The name for the layer. Names attributed to layers in the same project must be unique. By default, the name of the associated spatial data source is used.
Description	An optional text to describe the layer. In JMap applications, this text can be viewed by users in a mouseover bubble on the layer name.
Published	Determines if the layer is published or not. See <a href="#">Publishing layers</a> for more information.
Visible	Determines if the layer is visible or not when the project is opened. Users can make layers visible or invisible in JMap applications.
Selectable	Determines if elements of the layer will be selectable or not when the project is opened. Users can modify selection options in JMap applications. By default, the elements of the new layers that you create are not selectable.
Show in overview	Determines if the layer will appear in the map overview, if present. This overview simplifies map navigation.
Listed	Determines if the layer will be listed in the layer manager in JMap applications. A layer that is not listed appears on the map normally.

## Scale thresholds

Scale thresholds are used to control the visibility of a layer according to the scale of the displayed map. This is useful when you want to hide elements of a specific layer beyond (or under) a certain scale. For example, you might not want to display the local street layer when looking at the whole territory of a country. Using the thresholds, you could specify that the local streets are to be visible only when looking at a map with a scale greater than 1 : 100 000. In that case, you would specify a minimum scale of 1 : 100 000, without indicating a maximum scale.

Scale thresholds	
Minimum scale	Minimum scale in order for the layer to be visible. Allows the layer to become invisible when the user zooms out too much.
Maximum scale	The maximum scale in order for the layer to be visible. Allows the layer to become invisible when the user zooms in too much.
Non modifiable	(Applies to JMap Pro only) Determines if the users are allowed to modify these values. Modifying these scales on the JMap Pro side for layers that contain a high number of elements could cause very long queries that

	use a lot of resources or even lead to unusual responses from the JMap Pro application or JMap Server.
--	--

## Dynamic refresh

The dynamic refresh of the layer is used to automatically reload the data of a layer after a configured delay, without the need for the user to manipulate the map. This can be useful for layers that contain data that is updated regularly, such as layers of vehicle tracking (AVL). This is an alternative to the use of layers by region to have dynamic data.

Dynamic refresh	
Dynamic	Select this option to activate the dynamic refresh.
Refresh every	Specify the delay between each refresh.

## Dynamic Filters

Dynamic filters are used to display certain elements of the layer that match the user's criteria. JMap Pro applications support dynamic filters for layers that load by region or tile. JMap Web applications support dynamic filters for layers that load by region.



Dynamic filters are defined using an attribute, an operator, and values for the attribute. A dynamic filter can be composed of several attributes. Operators vary depending on the attribute type.

Text-type attributes provide full or partial match operators as well as the presence of null values. Up to 2048 unique values are supported in drop-down menu mode. For attributes who have more unique values than this number, value selection is done by entering the values in the range.

Numeric type attributes offer quantitative operators.

Date type attributes provide time operators and calendars for choosing dates. Dynamic time operators can also create mobile windows from a selected date.

To create a dynamic filter:

1. Press **Dynamic Filters** in the layer settings menu.
2. Click on the plus icon  to add an attribute.
3. Select an operator and values in the appropriate ranges. You can add as many attributes as you want. To remove an attribute from the filter, select it and click on the minus icon .
4. Check the **Enabled** box to make the dynamic filter active when a user opens a JMap Pro or JMap Web application.

5. Click on **Save** to save the dynamic filter.

## Style

---

The style of a layer determines the graphical representation of its spatial elements on the map. For example, the style of a line is determined by its thickness, color, dash pattern, etc. In JMap, each layer can have multiple styles. The style used depends on several factors.


Different styles can be configured for different scales. For example, a layer can have a single style for all scales while another layer can have one style for scales greater than 1:20000 and another style for scales smaller than or equal to 1:20000.


Layers also have selection styles. These styles are used to display selected elements at different scales. The selection styles are generated automatically from the layer styles but they can be customized for each layer.

The presence of thematics on a layer will override the layer styles. When a thematic is active on a layer, the style of each element is determined by the value of its attributes and the thematic's parameters. See [Creating Thematics](#) for more information.

### Managing layer styles

You can define one or more styles for a layer. If there are many styles, each one will be used within a certain range of scales. By default, one style exists for each layer and it covers the full possible scale range. To manage the styles of a layer, press **Style** from the layer settings menu.

To add a new style, press . In the style configuration interface, you must define the maximum scale from which the new style will be used. Its minimum scale will automatically be set to infinity or to the maximum scale of the next style.

To remove a style, select it from the list and press . Note that the greater scale style cannot be deleted. When deleting styles, the remaining styles will be adjusted to cover the full possible scale range.


Once you have configured one or more styles, you can click on **Create template** (located to the right of each style) to create a new style template from one of the layer's styles. The style template will automatically be linked to the layer. See [Style Templates](#) for more information.

### Creating/Modifying a style

You have the option to use an existing style template or to configure your own style. If you want to use a style template, click on **Use a style template**. You will then choose to refer to it or to copy it.


If no style template is used, you need to configure the parameters that will define the style. Style configuration interfaces are different depending on the type of element (points, lines, polygons, text, etc.). Some style parameters are common to many element types but others are specific to certain types.

**Antialiasing** is a method of representing perfect, continuous vectors on imperfect, discontinuous display devices so that they look as perfect as possible. In every style configuration section in JMap Admin, antialiasing is enabled by default, which improves the appearance of your maps. However, display performances are reduced when antialiasing is enabled, so use it judiciously.



*Example of polygon border without antialiasing (left) and with antialiasing (right)*


Partial object **transparency** can be used for every type of map element. A map element with a transparency value of 0% will be completely opaque while one with a 100% value will be invisible.



*Example of polygon with 50% (left) and 10% (right) transparency*

## Styles for points

Style parameters for points	
Symbol	<p>Select the symbol that will be used to represent the elements. The symbol can be a vector symbol or an image.</p> <p>Vector symbols are provided with JMap and offer special features. They can be resized without distortion and their border and fill color can be modified. However, they cannot be customized easily.</p> <p>JMap offers image libraries, which include SVG images. These image libraries are accessed under the <b>Images</b> tab. You can also provide your own image libraries. Their quality will be decreased if they are resized, unless you use SVG images. To provide your own images, place them in the following directory:</p> <pre>JMAP_HOME/JMapAdmin/icons</pre>

	<p>Supported image formats are svg, gif, png and jpeg. If subdirectories are created, they will be seen when browsing the image directory. This allows you to organize your image library.</p> <p>You can also upload new images by clicking on  in the symbol selection window. The maximum image size is 100 Mb.</p>
Size	Specify the size of the symbol. A value of 1 corresponds to the original size of the symbol or image.
Proportional size	Select this option if you want the size of the displayed symbols to vary in proportion with the map scale. You must enter the reference scale that will display the normal size of the symbols.
Use antialiasing	Select this option to activate antialiasing.
Transparency	Specify the partial transparency of the symbol.
Offset (x,y)	Adjust the original point of the symbol by offsetting the symbol by X and Y according to the specified values. The original point corresponds to the exact coordinates of the point element.
Rotate symbol with the map	Select this option to have the symbol rotated when the map is rotated. If this option is not selected, the symbol will always have its default angle, regardless of the map rotation.
Rotation	Specify the rotation to apply to the symbol.
Border thickness	(For vector symbols only) Specify the border thickness of the vector symbol.
Border color	(For vector symbols only) Specify the color of the lines of the vector symbol.
Transparent fill	(For vector symbols only) Select this option to have the inside of the vector symbol completely transparent.
Fill color	(For vector symbols only) Specify the color of the interior of the vector symbol.

## Styles for lines

Style parameters for lines	
Transparency	Specify the partial transparency of the line.

Arrow type	Specify the arrow option to use: <b>None:</b> No arrow. <b>Forward:</b> Place an arrow on the line pointing toward the last point of the line. <b>Backward:</b> Place an arrow on the line pointing toward the first point of the line.
Arrow position	If an arrow is used, determines the relative position of the arrow. A value of 50% places the arrow in the center of the line.
Line thickness	Specify the thickness of the line, in pixels.
Line color	Specify the color of the line.
Stroke style	Specify the stroke style (dashed, solid, with border, etc.) to use to draw the line. JMap provides many stroke styles.
Border thickness	If the line has a border, specify its thickness.
Border color	If a line stroke with a border is used, specify the color of the border.

## Styles for polygons

Style parameters for polygons	
Use antialiasing	Select this option to enable antialiasing.
Transparency	Specify the partial transparency of the polygon.
Transparent fill	Select this option to have the inside of the polygon completely transparent.
Fill color	Specify the color of the interior of the polygon.
Stroke style	Specify the stroke style (dashed, solid, with border, etc.) to use to draw the border of the polygon. JMap provides many stroke styles.
Border thickness	Specify the thickness of the borders of the polygon.
Border color	Specify the color of the border of the polygon.
Pattern	Specify the fill pattern to use. JMap provides many patterns.



Pattern color	If a pattern is used, specify the color of the pattern.
Transparent pattern fill	If a fill pattern is used, select this option to make the pattern background completely transparent.

### Styles for annotations

Style parameters for text	
Use antialiasing	Select this option to enable antialiasing.
Transparency	Specify the partial transparency of the text.
Font	Specify the font used to display the annotation text.
Bold	Select this option to use bold text.
Italic	Select this option to use italic text.
Underlined	Select this option to use underlined text.
Striked through	Select this option to use strikethrough text.
Outlined	Select this option to use outlined text. Outlined text has an outline that may be of a different color. This helps make the text on the map more readable.
Outline color	If outlined text is used, specify the color of the outline.
Text color	Specify the color of the text.

### Styles for images

Style parameters for images	
Transparency	Specify the partial transparency of the image.

### Selection style

There is a selection style for each style of the layer. The selection styles are used to represent the elements when they are selected on the map. By default, the selection styles are generated automatically using the layer's basic styles and the project's default selection color.

To modify the selection style, unselect the **Generate from default style** option and adjust the style parameters as needed.

## Analysis

In addition to configuring the style of a layer, you can also create graphical representations to analyze the distribution of point data.

### Clustering

Clustering, as its name implies, creates clusters of points on the screen. Special symbols are used to graphically represent these clusters on the map and display the number of elements they contain.

Parameters	
Distance	Minimum distance (in pixels) between 2 points in order for them to form a cluster.
Minimum elements	The minimum number of elements required to create a cluster.
Symbol	Symbol used to represent a cluster on the map.
Label	The settings of the label (font, color, etc.) that will display the number of elements in a cluster.

### Heat maps

Heat maps are used to graphically represent the concentration distributions of a type of object or event on the territory. The more the color of a zone is intense, the more the concentration is high.

Parameters	
Radius	The radius used to display the density map around each point.
Weight	Numeric attribute that determines the weight of each point to display the density map. The more the weight is high, the more the color is intense. This parameter is optional.
Opacity	Determines the degree of opacity for the display of the density map.
Intensity	Defines the intensity of the colors based on the concentration of points. If the intensity is lower, more points will be needed to produce intense colors.

Display points	Allows you to display the points of the layer under the density map. The points will be hidden by the density map if the opacity is very high.
----------------	--

## Thematics

Thematic mapping is the production of maps to express information about a specific phenomenon. Examples of thematic maps include: polygons representing sectors of a city colored differently based on the crime rate of each sector; points representing cities displayed using different symbol sizes based on the population in the city, etc. In JMap, you can create thematic maps using the bound attributes of a layer. Depending on the values of their attributes, map elements will then be displayed differently. Using JMap Admin, you can create as many thematic maps as you want and you can also create many thematics using the same layer.

In JMap, there are 2 main categories of thematics: [classifications](#) and [proportional quantities](#).


To create a thematic, press **Create** in the **Thematics** section of the layer settings.

New thematic	
Name	Enter a unique name for the thematic. This name will be visible by users.
Description	You can provide a description for the thematic.
Type	Select the type of thematic you wish to create. The following steps will depend on the type of thematic you have chosen.

### Classification

Thematics that use a classification will separate map elements into a finite number of categories (also called classes), each having a specific style. When a map element belonging to such a thematic is displayed, it uses the style of the category it is part of in order to render itself on the screen.

## Creating a graduated styles thematic



Graduated styles thematics use a graduation of one or more visual variables to represent the elements of the different categories. Examples of such graduations include: the fill color of polygons that is graduated from white to red, the size of point symbols that is graduated from size 1 to size 5, the line width of elements that is graduated from 1 to 4, etc. In all cases, there is a finite number of categories and every element of the layer falls into one of those categories. Only a numeric attribute can be used for this type of thematic.

To create a new thematic of this type, you need to select the numeric attribute to use, define the number of categories, select the range calculation method, and define the category styles.

There are several methods for calculating the ranges of values for the categories of this type of thematic. See [Methods for calculating ranges](#) for more information.

Attribute	
Attribute	Select the numeric bound attribute to use.
Do not draw elements with out-of-sample values	If this option is selected, elements with values outside of the value range will not be displayed. This can happen when the data is modified after the thematic was created.
Create a category for null values	Select this option if you want null values to be represented in the thematic.

Categories	
Categories	Enter the desired number of categories.
Range method	Select the method used to determine the bounds of the value ranges. Refer to <a href="#">Methods for calculating ranges</a> for more information.

Remove duplicated categories	In some cases, several categories can have the exact same value limits. Select this option to avoid having identical categories. This can happen with very small data sets or if limits are rounded to big numbers.
Round at	Select the precision to use to round category range limits. It is often more useful to have rounded limits than very precise ones (e.g. country populations rounded to the nearest million).

The next section allows you to define the styles of the categories. There are two possibilities: create custom range styles or use predefined color schemes.

### Custom range styles

You must define the from and to values of the style by indicating the style variables that will vary (e.g. border thickness, symbol size, fill color, etc.). The category styles are then generated by interpolation between the from and to styles. Optionally, a third style can be used to create an inflexion point. If an inflexion is defined, the generated styles will pass through the inflexion point at the specified position in percentage. The interface is different based on the element type of the layer.

Custom range styles	
Use inflexion point at	Select this option to use an inflexion point and specify the position of the inflexion.
Edit base style	Use this link to modify the style of the layer without leaving the Thematics section. The base style is used to produce the styles of the categories.

### Color schemes

Instead of manually defining styles, you can select a color scheme to generate the styles of the thematic's categories.

Color schemes	
Type	<p>3 types of color schemes are available:</p> <p><b>Sequential:</b> The colors form a gradient of sequential colors (e.g. from white to red).</p> <p><b>Diverging:</b> The colors form a gradient with a central color (e.g. from blue to white to red). Here emphasis is placed on central categories.</p>

	<b>Qualitative:</b> Colors do not follow any sequence.
Apply to	You can choose to apply the palette to the available visual variables (e.g. fill, border, etc.), depending on the type of element on the layer.

### Creating a graduated symbols thematic




Graduated symbols thematics draw symbols superposed on the elements they qualify. The symbol sizes are graduated according to a finite number of categories based on a numeric attribute. The symbols can be used with any type of map element. Only numeric attributes can be used for this type of thematic.

There are several methods for calculating the ranges of values for the categories of this type of thematic. See [Methods for calculating ranges](#) for more information.

The creation process is the same as for [creating a graduated styles thematic](#), as described above.

## Creating an individual values thematic



*Examples of thematics using individual values classification*

Individual values thematics represent all elements that have the same attribute value with the same style. This type of thematic is not using a range of values for each category but rather a specific value. The maximum number of unique different values is 512. If your layer has more different values, it will not be possible to create this type of thematic on that layer. Numeric and alphanumeric attributes can be used with this type of thematic.

To create a new thematic of this type, basically all you need to do is to select the attribute to use.

Individual values thematic	
Attribute	Select the bound attribute to use. It can be numeric or alphanumeric.
Do not draw elements with out-of-sample values	If this option is selected, elements with values not present in the value sample will not be displayed. This can happen when the data is modified after the thematic was created.
Create a category for null values	Select this option if you want null values to be represented in the thematic.

JMap proposes random colors for this type of thematic. You can modify styles manually or click on **Color Schemes** to use a predefined color scheme.

## Creating an individual custom values thematic

Individual custom values thematics are similar to individual values thematics except that you can define your own values, instead of being limited to values already present in the data. This is useful


when you create thematics using a data set that does not contain all the known possible values for an attribute. When new data is later added to this data set, the new values will be handled properly by this type of thematic.

The creation process is similar to [creating an individual values thematic](#), except that you have the option to modify the list of individual values by adding, removing or modifying categories.

### Proportional quantities

Proportional quantities thematics represent map elements using a continuous variation of a visual variable (e.g. symbol size, fill color, etc.) based on a numeric attribute or set of attributes.

### Creating a proportional symbols thematic




Proportional symbols thematics draw circular symbols superposed on the center of the elements they qualify. The symbol sizes are determined by interpolation between the minimum and maximum values of the attribute. Only numeric attributes can be used for this type of thematic.

To create a new thematic of this type, you need to select the numeric attribute to use and define the from and to styles. The symbol size and color will be interpolated between the from and to values.



## Creating a pie charts thematic



Pie charts thematics draw pie chart diagrams on the center of the elements they qualify. This type of thematic works with one or many numeric attributes. Each part of the diagram (piece of the pie) is associated with a different attribute. The size of the diagram is proportional to the sum of the attribute values. Only numeric attributes can be used for this type of thematic.


To create a new thematic of this type, you need to select one or more numeric attributes to use and define the chart style.

Pie charts thematic	
Attributes	Select one or more numeric attributes. Each attribute will be represented by a piece of the pie chart. The size of the chart will be determined by the sum of those attribute values.
Do not draw elements with out-of-sample values	If this option is selected, elements with values not present in the value sample will not be displayed. This can happen when the data is modified after the thematic was created.
Ignore negative values	Select this option to ignore negative values.

Pie chart style	
Chart size	Select the from size (smaller) and the to size (bigger). The chart size will be determined by interpolation between these two values.
Border thickness	To draw a border around the chart, select a non zero border thickness.

Start angle	Select one of the directions to use as the starting angle of the chart. The first piece of the pie chart will start at the specified angle.
Draw shadow	Select this option to draw a shadow for the pie charts.
Labels	Select the label type (or none) to indicate the value or relative percentage of each piece of the pie chart.
Colors	Select the color of each portion of the pie chart.

### Creating a bar charts thematic



Bar charts thematics draw bar chart diagrams on the center of the elements they qualify. This type of thematic works with one or many numeric attributes. Each bar of the diagram is associated with a different attribute. The size of the diagram is proportional to the sum of the attribute values. Only numeric attributes can be used for this type of thematic.

The creation process is similar to [creating a pie charts thematic](#), as described above.

### Methods for calculating ranges


Several different methods can be used to calculate the ranges of values for the categories of thematics using classifications. These methods are described below.


Method	Description
Equal ranges	The ranges will have equal sizes between the minimum and the maximum values (e.g. 0-10,10-20, 20-30).

Equal count	The range limits will be calculated so that an equal count of elements falls in each category.
Standard deviation	The range limits will be calculated so that the average value falls in the middle of the categories and each category range size is equal to the calculated standard deviation value.
Defined interval	The range size is user-defined and constant for all categories, starting from the minimum value, and adding the defined interval for each category.
Percent ranges	The range for each category is expressed as a percentage of the full value range (e.g. 4 categories with 20%, 20%, 35% and 25%). The total must be equal to 100%.
Custom ranges	All range limits are user-defined.

Once the thematic has been created, you are brought to the interface that displays its general information and that allows you to specify the legend, give titles to the classes, and edit or delete the thematic.

<b>Legend</b>	
Legend title	Enter a title for the legend.
Legend subtitle	Enter a subtitle for the legend.
Dynamic legend	For classification thematics only. Select this option to make the legend dynamic. This type of legend is constantly refreshed to show only the classes that are visible on the map displayed.
Symbols in the legend	For proportional quantities thematics only. Select the number of symbols you want to display in the legend. The minimum is 2 symbols indicating the extreme values.

Click on  to save the settings.

For classification thematics, you can unselect classes you do not want to display, and you can also give a title to each class. Click on  to save the settings.

## Enabling and disabling thematics

Enabled thematics are displayed automatically when the layer is displayed in JMap on the client. Disabled thematics are still available but are not displayed by default. They need to be enabled by

the user to be displayed. You can enable and disable thematics from the thematics section in JMap Admin.

## Reordering thematics

In JMap applications, thematics are displayed in the order they are defined in JMap Admin. It is important to set the order appropriately because some thematics can completely hide others if they are placed on top. Use the **Modify** menu from the list of thematics in order to modify their order.


## Labels

In JMap, labels are text that is related to map elements. They are used to display information about the elements on the map. For example, you can use labels to display the city names for a layer of points representing cities.

Labels can either be placed manually using the labeling tool or generated automatically by JMap at display time. Depending on the type of elements of the layer, the labeling configuration section can slightly vary.



Example of curved labels (left) and labels with a frame (right)



Example of labels with a background symbol

Labeling is configured by specifying text that defines the label's content; this text can contain static parts, variable parts (functions) and JavaScript programs. At display time, functions are executed and replaced by the result. For example, the `ElementValue(attrib)` function (or `ev(attrib)`, in its short form) will be replaced by the value of the corresponding attribute. JavaScript programs can be used to perform operations on attribute values. Label text can span multiple lines.

The functions supported by labels are the same as those supported by mouseover. For more information on these functions, refer to the [Mouseover](#) section.

Labeling parameters	
Label text	<p>The text of the label. Static parts will be displayed as is and <code>ev(attrib)</code> functions will be replaced by the corresponding bound attribute values. Unlike mouseover bubbles, labels don't support HTML formatting or hyperlinks. See the following examples:</p> <pre>Country: ev(country)           Country: Canada City: ev(city)                 City: Paris (France)       (ev(country))           Population: 2150000 Population: ev(pop)</pre> <p>Labels also support JavaScript programming to perform mathematical operations as well as operations on character strings using attribute values. The <code>print</code> function is used to print content in the label.</p> <pre>Area: ev(area_km2) km2 &lt;script&gt; var SQ_KM_IN_SQ_MI = 2.58998811; var area_sq_mi = ev(area_km2) / SQ_KM_IN_SQ_MI; print(area_sq_mi.toFixed(1) + " sq. mi"); &lt;/script&gt;</pre> <p>leads to</p> <pre><b>Area :</b> <b>91935.7 km2</b> <b>31635.6 sq. mi</b></pre>

Label style	
Font	Select the font to use to display the labels.


Size	Select the size of the font.
Bold, Italic, Underline, Striked through	Select the font attributes.
Outlined	Select this option to display an outline around the label text. This makes it easier to read labels on the map.
Use antialiasing	Select this option to enable antialiasing.
Text color	Select the color of the label text.
Outline color	If the <b>Outlined</b> option is selected, choose the color of the outline. White is the default.

## Automatic labeling

Automatic labeling adds labels to map elements automatically, without user interaction. For each vector layer, you can enable or disable automatic labeling and define scales between which automatic labeling will be activated. It is often useful to set a minimum scale limit for automatic labeling to avoid overcrowding the map.

Also, in order to avoid overcrowding the map, three tools allow you to control the order or priority in the position or display of the labels: dynamic position, layer priority, and priority by attribute.

Automatic labeling	
Automatic labeling	Select this option to enable automatic labeling.
Minimum scale	Minimum scale over which automatic labeling will be activated.
Maximum scale	Maximum scale under which automatic labeling will be activated.
Label position	<p>The position of the label in relation to the map element is determined based on a grid, with nine possible positions. This position can be fixed or dynamic.</p> <p><b>Fixed:</b> the label is always displayed at the selected position. This is the default option.</p> <p><b>Dynamic:</b> this function allows you to display the maximum number of labels avoiding overlapping conflicts of labels. The position of the labels of the layer varies according to the relative priority established for each position of the grid. Possible values are: 0 Blocked, 1 High, 2 Medium, and 3 Low.</p>

	<p>The default value of the center position is 1. At first JMap attempts to place the label in the center position. If this position is occupied by another label, JMap places the label in another lower priority position (Medium or Low) to minimize conflicts.</p>
Label offset	Enter an offset in X and Y to modify the position of the label text.
Layer priority	<p>This parameter allows you to assign the layer a priority over other layers for displaying its labels. This priority is relative, depending on the other layers that are present. The available values, from lowest to highest priority, are the following: Normal, Above Normal, High, Very High, Maximum. For example, the labels of a layer with a High priority are displayed before the labels of a layer whose priority is lower (Normal or Above Normal).</p>
Priority by attribute	<p>This parameter allows you to assign a display priority to the elements of a layer based on the value of an attribute. This priority is relative and depends on the other elements that are present in the same layer. For example, in a road network layer in which road sections are categorized according to their importance, the labels of the most important sections have a higher display priority than the labels of the less important sections.</p> <p>The attribute can be numeric or alphanumeric, and it must be possible to organize the values in ascending or descending order.</p> <p>Check this option to select the attribute to use for the prioritization in the drop-down menu. This icon  is used to establish whether the priority gradient is in the ascending or descending direction of the values.</p>
Allow labels overlapping	Allow the labels of one layer to overlap and to overlap the labels of other layers. This option overrides the global project setting that prevents label overlapping. This can be useful to ensure that all labels of this layer are displayed.
Prevent label duplication	Select this option to avoid having the same label text displayed many times. Useful for displaying street names.
Parse numeric labels	If label contains text and numbers, display only numeric values. Useful when you want to display only highway numbers using an attribute containing other text (e.g. "Highway 40" becomes "40").
Oriented labels (along the line)	Only for line elements. Select this option to display the label text along the lines.
Curved labels	Only for line elements. Select this option to have the label text follow curved lines.

Proportional size	By default, label text is always displayed at the specified font size, independently of the scale of the map. Use this option to have the label text size adjusted proportionally to the scale of the map. The text will be displayed at its specified font size when looking at the map at the specified reference scale. When the scale of the displayed map is changed, the text size will be modified accordingly.
Background symbol	Select this option in order to choose a symbol that will be displayed behind the label text. Note that the label text should fit in the selected symbol. This is used mainly for highway shields containing highway numbers.
Draw frame	Select this option to draw a frame around the label text. You can also select the color of the background of the frame as well as the color of its border.
Rotation	Select this option if you want the labels to have a rotation.  <b>Angle attribute:</b> You can select a numeric bound attribute that contains the rotation angle of the text. The labels will follow this rotation.  <b>Rotation direction:</b> If an angle attribute is used, select the direction of the rotation.
Follow map rotation	Select this option to have the labels rotated with the map if the user sets a map rotation.
Follow symbol position	Check this option if you want the labels to follow the symbol when an offset is applied to it.

## Mouseover

---

Mouseover bubbles are meant to display information about the elements they are pointing to. This information includes text, attribute values, hyperlinks, images, etc. The JMap administrator determines what information is displayed in the bubbles of each layer.





The content of mouseover bubbles can be formatted using HTML tags. Mouseover bubbles can also contain JavaScript programs.

To configure mouseover for a layer, click on **Mouseover** in the details section of the layer.

<b>Mouseover</b>	
Mouseover	Enter the content of the mouseover bubble. See sections below for an explanation of the syntax.
Background color	Select the background color of the mouseover bubble.
Prevent text duplication	Select this option to prevent the same text from being repeated many times within the same bubble. This can happen when pointing to many map elements on the same layer that have the same mouseover content (e.g. street segments at an intersection).
Minimum scale	Activate this option and enter the minimum scale from which the mouseover bubble must be displayed.
Maximum scale	Activate this option and enter the maximum scale from which the mouseover bubble must be displayed.

## Providing mouseover content

You must provide the text that will be used as the content of the bubble. This text can be comprised of static parts (displayed as is), variable parts (replaced at display time by another value), simple JavaScript programs, and HTML tags. For instance, the `elementValue(city)` function will be replaced at display time by the value of the city attribute for the pointed element.

## Mouseover syntax

The mouseover syntax is comprised of various functions that will determine the content of the bubbles. Functions and their parameters are generally not case sensitive. For instance, `ev(city)` is equal to `Ev(CITY)`.

The following table explains the various available functions:

Function	Description
<b>elementValue</b> ( <i>attrib</i> ) or <b>ev</b> ( <i>attrib</i> )  <i>attrib</i> : the name of an attribute	Replaced by the value of the bound attribute whose name is passed as a parameter for the pointed element. For example, <code>ev(id)</code> will be replaced by the value of the <code>id</code> attribute for this element.
<b>elementId</b> ()	Replaced by the element identifier.
<b>polygonArea</b> ()	Replaced by the area of a pointed polygon type element.
<b>lineLength</b> ()	Replaced by the length of a pointed line type element.
<b>centroid</b> ()	Replaced by the coordinates of the geometric centroid of the element's geometry.
<b>format</b> ( <i>attrib, format</i> )  <i>attrib</i> : the name of a date or numerical attribute  <i>format</i> : the desired date format	Replaced by a number or date that was formatted according to a specific format.  <b>Example:</b> <code>format(date_insp, dd/MM/yyyy)</code>  where <code>date_insp</code> is the name of an attribute containing a date and <code>dd/MM/yyyy</code> is the desired date format, as indicated in the documentation of the <a href="#">java.text.SimpleDateFormat</a> Java class.  <b>Example:</b> <code>format(attrib, ##0,00)</code>  where <code>attrib</code> is the name of an attribute containing a number and <code>##0,00</code> is the desired number format, as indicated in the documentation of the <a href="#">java.text.DecimalFormat</a> Java class.
<b>ifNull</b> ( <i>attrib, value</i> )  <i>attrib</i> : the name of the attribute to test  <i>value</i> : the value to display if <i>attrib</i> is null	Replaced by the value only if the value of the <i>attrib</i> attribute is null. If the attribute value is not null, nothing is displayed.  <b>Example:</b> <code>ifNull(temp, N/A)</code>  Displays N/A if the value of the <code>temp</code> attribute is null.  <b>Example:</b> <code>ifNull(attrib_a, attrib_b)</code>  Displays the value of the <code>attrib_b</code> attribute if the value of the <code>attrib_a</code> attribute is null.

<p><b>ifNotNull</b>(<i>attrib</i>, <i>value</i>)</p> <p><i>attrib</i>: the name of the attribute to test</p> <p><i>value</i>: the value to display if <i>attrib</i> is not null</p>	<p>Replaced by the value only if the value of the <i>attrib</i> attribute is not null. If the attribute value is null, nothing is displayed.</p> <p><b>Example:</b> <code>ifNotNull(land_value, \$)</code></p> <p>Displays \$ only if the value of <i>land_value</i> is not null.</p>
<p><b>subString</b>(<i>attrib</i>, <i>startIx</i>, <i>endIx</i>)</p> <p><i>attrib</i>: the name of the attribute for which a part must be extracted.</p> <p><i>startIx</i>: starting position in the character string.</p> <p><i>endIx</i>: ending position in the character string.</p>	<p>Replaced by a portion of the value (as a character string) of the <i>attrib</i> attribute, between the <i>startIx</i> position and <i>endIx</i> position.</p> <p><b>Example:</b> <code>subString(name, 0, 5)</code></p> <p>Replaced by the first five characters of the name attribute value. If this value is <i>Montreal</i>, the mouseover will display <i>Montr</i>.</p>
<p><b>encode</b>(<i>attrib</i>, <i>encoding</i>)</p> <p><i>attrib</i>: the name of the attribute to code</p> <p><i>encoding</i>: the name of the encoding</p>	<p>Replaced by the value of the <i>attrib</i> attribute once it is encoded with the specified character <i>encoding</i> (UTF-8, CP437, ISO 8859-1, etc).</p> <p><b>Example:</b> <code>encode(name, UTF-8)</code></p> <p>Replaced by the value of the <i>name</i> attribute encoded in <i>UTF-8</i> characters.</p>
<p><b>&lt;script&gt;</b> code <i>JavaScript</i> <b>&lt;/script&gt;</b></p>	<p>Runs the <i>JavaScript</i> code found between the tags. In <i>JavaScript</i>, the attribute values of the elements are accessible through the <b>elementValue()</b> or <b>ev()</b> function.</p> <p>Mathematical operations or character string operations can be performed on attribute values. To display content in the bubble, the script must call on the <b>print()</b> function.</p> <p><b>Example:</b> <code>&lt;script&gt; print ( ev(population) / ev(area) ); &lt;/script&gt;</code></p> <p>Calculates and displays the result of the value of the <i>population</i> attribute divided by the value of the <i>area</i> attribute.</p> <p><b>Example:</b> <code>&lt;script&gt;</code>  <code>var KM_IN_MI = 0.621371;</code>  <code>var dist_mi = ev(km) * KM_IN_MI;</code>  <code>print('ev(osm_name)');</code>  <code>print(dist_mi.toFixed(1) + " mi");</code>  <code>&lt;/script&gt;</code></p>

	Converts the distance in kilometers contained in the value of the <i>km</i> attribute into miles. Displays the value of the <i>osm_name</i> attribute and the distance in miles with a decimal figure.
<b>&lt;a href="download:file URL"&gt;some text&lt;/a&gt;</b>	<p>JMap supports a special hyperlink syntax that allows a user to download a file by clicking on the link. The file to download can come from a <i>http</i>: or a <i>file</i>: URL.</p> <p><b>Example:</b> <code>&lt;a href="download:http://someserver/123/report.pdf"&gt;Download&lt;/a&gt;</code></p> <p>Displays a link that can be used to download the <i>report.pdf</i> file from the web.</p> <p><b>Example:</b> <code>&lt;a href="download:file://D:/123/report.pdf"&gt;Download&lt;/a&gt;</code></p> <p>Displays a link that can be used to download the <i>report.pdf</i> file from a Windows file system folder.</p>
<b>photos()</b>	Replaced by hyperlinks that allow you to open or download the images attached to the element. These images are photos taken on JMap Mobile or JMap Survey, or images selected with JMap Pro and associated with map elements.
<b>photosAsThumbnails()</b>	Replaced by smaller versions of the images attached to the element. The user can click on a thumbnail to open the full size image.
<b>projectName()</b>	Replaced by the name of the current project.
<b>userName()</b>	Replaced by the user code of the user that is currently connected.
<b>sessionId()</b>	Replaced by the identifier of the current session.
<b>host()</b>	Replaced by the name of the host or address of the JMap Server instance to which the application is connected.
<b>port()</b>	Replaced by the port number (http or direct) of the JMap Server instance to which the application is connected.
<b>date()</b>	Replaced by the current date and time.




## HTML content

The content of the bubble can be formatted using simple HTML tags. Mouseover bubbles do not support CSS or advanced tags such as `<DIV>`. The following HTML tags are supported and frequently used in mouseover:

<B>, <b>, <U>, <A>, <IMG>, <BR>, <TABLE>

You can insert hyperlinks in mouseover bubbles. These hyperlinks can be clicked, and they allow users to open HTML pages or to open or download files.

### Examples

Mouseover content	Display
<p><b>City : ev(CITY)</b></p> <p>A simple example of static text with the value of an attribute.</p>	
<p><b>City: ev(CITY)</b> <b>(ev(COUNTRY))</b></p> <p>Example containing static parts and displaying 2 attribute values on 2 lines.</p>	
<p><b>&lt;b&gt;ev(STATION_NAME)&lt;/b&gt;</b> <b>&lt;a href="ev(URL)"&gt;Site web&lt;/a&gt;</b></p> <p>An example of basic formatting using HTML tags and a hyperlink where the URL comes from the value of the URL attribute.</p>	

```
<b>ev(DESCRIPTION)</b>
```

```

```

An example of an HTML tag that takes the image URL from the value of the IMAGE\_URL attribute.



Area :

```
ev(AREA_KM2) km2
```

```
<script>
```


```
var SQ_KM_IN_SQ_MI = 2.58998811;
```

```
var area_sq_mi = ev(AREA_KM2) /
SQ_KM_IN_SQ_MI;
```

```
print(area_sq_mi.toFixed(1) + " sq. mi");
```

```
</script>
```

An example of a <script> tag with JavaScript code. The value of the AREA\_KM2 attribute is converted from square kilometers to square miles.




```
table style="border:3px solid black; border-
radius:5px; background: #1fc8db;
color:white ">
```

```
<thead> <tr> <th class="">Name</th> <th
class="actions">FirstName</th> </tr>
</thead>
```

```
<tbody> <tr> <td class="">Gratton</td> <td
class="actions">Bob</td> </tr> </tbody>
```

```
</table>
```

An example of formatting with a style attribute.



## Locating map elements or coordinates using mouseover

Mouseover supports a function to locate map coordinates or elements using a special URL syntax. A hyperlink is displayed in the bubble, and when it is clicked, the map locates the specified element(s) or region. This function is only available in JMap Pro.

Mouseover locate example	Description
<code>&lt;a href="locate:region;-73;45;5;5"&gt;Locate&lt;/a&gt;</code>	Displays a <i>Locate</i> hyperlink. When clicked, locates the region defined by $x=-73$ , $y = 45$ , $width = 5$ , $height = 5$ in the same map. This is expressed in the map's units.
<code>&lt;a href="locate:object;subway;name;'atwater'"&gt;Locate&lt;/a&gt;</code>	Displays a <i>Locate</i> hyperlink. When clicked, locates the elements on the subway layer that have their attribute name equal to <i>atwater</i> in the same map.
<code>&lt;a href="locate:object;subway;name;'a%"&gt;Locate&lt;/a&gt;</code>	Displays a <i>Locate</i> hyperlink. When clicked, locates the elements on the subway layer that have their attribute name starting with letter <i>a</i> in the same map.
<code>&lt;a href="locate:object;subway;name;'atwater';1000"&gt;Locate&lt;/a&gt;</code>	Displays a <i>Locate</i> hyperlink. When clicked, locates the elements on the subway layer that have their attribute name equal to <i>atwater</i> in the same map. The resulting map has a scale of 1 : 1000.
<code>&lt;a href="locate:object;subway;name;'atwater':target=Result"&gt;Locate&lt;/a&gt;</code>	Displays a <i>Locate</i> hyperlink. When clicked, locates, in a new map called <i>Result</i> , the elements on the subway layer that have their attribute name equal to <i>atwater</i> . If a map called <i>Result</i> already exists, it is reused. If the name of the map was new, a new map (with an automatically generated name) would be created each time.


## Using a URL to display content

You can specify a URL that opens an HTML page to display in the mouseover bubble (only supported in JMap Pro). The HTML page will occupy 100% of the bubble. The syntax is as follows:

```
$URL{http://awebsite.com}
```

The specified URL can be static or it can come from an attribute. It can also use attribute values as parameters, as shown below:

```
$URL{http://awebsite.com?param1=ev(ATTRIB_A)&param2=ev(ATTRIB_B)}
```



An example of mouseover HTML content referred to by a URL

## Information Reports

Information reports are used to display descriptive information regarding map elements. These reports can display attributes extracted from the underlying spatial data source or information from databases outside JMap. Each layer can have zero, one or more reports. The information reports are presented as web pages or PDF documents.

To configure reports for a layer, click on **Reports** in the layer's details section.

The reports section shows the list of existing reports for a layer. In JMap applications, reports are presented in this order. You can change the order using the arrows. To create a new information report, press **Create**. To delete a report, press **Delete**.



### Creating a report

There are three different types of reports: **Basic**, **Advanced** and **Custom**.

#### Basic

Basic reports are generated as web pages. They contain features to be printed and exported in Excel. Tables containing the values can be sorted by clicking on the column headers. You can also configure the names of the fields to be displayed in the reports.



Countries							
Countries							
JMap Countries  							
COUNTRY ▲	CAPITAL	CONTINENT	POP_MALE	POP_FEM	POP_URBAN	POP_RURAL	LITERACY
Brazil	Brasilia	South America	74 992 000	75 375 000	112 743 000	37 624 000	81
Canada	Ottawa	North America	13 515 119	13 893 779	0	0	99
Chile	Santiago (CHL)	South America	6 716 822	6 882 606	11 573 878	2 025 561	93
Mexico	Mexico City	North America	39 893 969	41 355 676	0	0	87
Peru	Lima	South America	11 071 166	10 927 095	15 576 912	6 421 349	85
United States	Washington, D.C.	North America	125 897 610	132 010 327	0	0	97

*An example of a basic information report*

Configuration	
Title	The title of the report.
Extract data from	<p><b>Current layer:</b> Obtain report data directly in the layer attributes. Refer to <a href="#">Report data sources - Current layer</a>.</p> <p><b>External database:</b> Obtain report information from an external database connected to JMap. The database must contain a field that links to an attribute of the layer. Refer to <a href="#">Report data sources - External database</a>.</p>
Template (single)	Template used for reports on a single map element.
Template (multiple)	Template used for reports on multiple map elements.

Attributes	
Title	Text to be displayed in the report instead of the attribute name.

## Advanced


Advanced reports are based on the BIRT reporting tool (<http://www.eclipse.org/birt/>). A default report template is provided with JMap. You can also use the BIRT report Designer application to create custom reports or to edit the template provided in order to adapt it to your needs (add a logo,

change the colors, etc.). For more information on report development, visit the BIRT website (<http://www.eclipse.org/birt>).

Reports can be generated in HTML or PDF format. Geographic map integration is also supported.

Countries
Information

### Information



<u>COUNTRY</u>	<u>CAPITAL</u>	<u>CONTINENT</u>	<u>CODE</u>	<u>FIPS</u>	<u>POP_GRW_RT</u>	<u>POP_15_64</u>	<u>LITERACY</u>
United States	Washington, D.C.	North America	840.0	US	0.8	168363628	97.0
Canada	Ottawa	North America	124.0	CA	1.1	18448785	99.0

*An example of an advanced report with a map*

Advanced reports	
Format	<p><b>HTML:</b> The report is generated as a web page. Tools allow you to export and print the report's content. If the report is created for multiple map elements, its content can be sorted by clicking on the column headers.</p> <p><b>PDF:</b> The report is generated in PDF format. This format is better suited for printing because the page layout is better. However, the content of this type of report is more static compared to the HTML report.</p>
Title	The title of the report.

Extract data from	<p><b>Current layer:</b> Obtain report data directly from layer attributes. Refer to <a href="#">Report data sources - Current layer</a>.</p> <p><b>External database:</b> Obtain report data directly from an external database connected to JMap. The database must contain a field that links to an attribute of the layer. Refer to <a href="#">Report data sources - External database</a>.</p>
Template (single)	<p>Template used for reports on a single map element. Two templates are available:</p> <p><b>inforequest.rpttemplate:</b> Basic template containing a table, arranged vertically.</p> <p><b>inforequestMap.rpttemplate :</b> Similar to basic template but also contains a geographic map.</p> <p>Refer to <a href="#">Report templates (Advanced reports)</a>.</p>
Template (multiple)	<p>Template used for reports on multiple map elements. Two templates are available:</p> <p><b>selectionreport.rpttemplate:</b> Basic template containing a table, arranged horizontally.</p> <p><b>selectionreportMap.rpttemplate:</b> Similar to basic template but also contains a geographic map.</p> <p>Refer to <a href="#">Report templates (Advanced reports)</a>.</p>

### Report templates (Advanced reports)

With **advanced** reports, you can choose the report template you wish to use. By default, two templates are provided with JMap: a basic report template and a report template with an integrated geographic map. Each one of these templates is also available in two versions: one version is for a single element and the other is for a selection of multiple elements. You can create your own report templates based on the existing templates and add them to those provided by JMap. You can then select your templates to configure reports. The report template files (.rpttemplate) are placed in the **JMAP\_HOME/applications/templates/reports** directory. Your templates must be placed in the single or multiple sub-directory, depending on whether they are in single element or multiple element version.

### Custom

**Custom** reports are external to JMap and can be called using a URL. These reports can come from reporting tools (e.g. Crystal Reports, Jaspersoft, etc.) or from simple web pages.

A special syntax allows you to format the parameters to be passed in order to open the report.

General information	
Title	The title of the report.
Report URL	<p>Enter the URL that will allow you to open the external report. You will probably have to pass certain parameters in the report URL to identify the elements for which you wish to open a report. The parameter values usually come from the bound attributes of map elements. A special syntax is used to format the parameters.</p> <p>For example, if your report must be called by this URL:</p> <pre>http://myserver/reports/myreport?id=3</pre> <p>then, if the 0 attribute contains the parameter values, the following syntax must be used:</p> <pre>http://myserver/reports/myreport?id=%0</pre> <p>However, if your report can include information on a selection of multiple map elements, the parameter syntax can take one of two different forms. If your report must be called by the following URL:</p> <pre>http://myserver/reports/myreport?id=3,4,5</pre> <p>then, if the 0 attribute contains the parameter values, the following syntax should be used:</p> <pre>http://myserver/reports/myreport?%param[%0,'id',']</pre> <p>This syntax uses the expression %param[Attribute, Parameter, Separator].</p> <p>If your report must be called by this URL:</p> <pre>http://myserver/reports/myreport?id=3,id=4,id=5</pre> <p>then, if the 0 attribute contains the parameter values, the following syntax should be used:</p> <pre>http://myserver/reports/myreport?%param[%0,'id']</pre> <p>This syntax uses the expression %param[Attribute, Parameter].</p> <p>It is also possible to include other variables to compose the URL, such as %f, %p, %u, %h, etc. Refer to <a href="#">Supported variables</a> for more information.</p>

## Supported variables in the URLs of custom reports

Variable	Display
%n	Replaced by the corresponding bound attribute value for the element. For example, %0 refers to the 1st bound attribute, %1, to the second one, etc.
%f	<p>Replaced by a formatted number or date. There are 2 possible formats:</p> <p><code>%f[%n^D^dd/MM/yyyy]</code></p> <p>where %n refers to an attribute containing a date, D indicates that we want to display a formatted date and dd/MM/yyyy is the format pattern, as indicated in the Java class <a href="#">java.text.SimpleDateFormat</a> documentation.</p> <p><code>%f[%n^N^##0,00]</code></p> <p>where %n refers to an attribute containing a number, N indicates that we want to display a formatted number and ##0,00 is the format pattern, as indicated in the Java class <a href="#">java.text.NumberFormat</a> documentation.</p>
%p	Replaced by the currently opened project name.
%u	Replaced by the name of the user currently logged in.
%s	Replaced by the current session id.
%h	Replaced by the host name or address of the JMap Server instance the client is connected to.
%o	Replaced by the port number (http or direct) of the JMap Server instance the client is connected to.
%t	Replaced by the current time (date and time).

## Report data sources

**Basic** and **advanced** reports can take their data from layer attributes or from an external database connected to JMap.

### Current layer

Select the **Current layer** option to create a simple report that will only query the layer attributes (read below for the External database option). Afterwards, select the attributes to include in the report using the check boxes. Only the selected attributes will be displayed to the user; the others

will be excluded from the report. Lastly, you can specify titles for the attributes; these will be displayed to the user instead of the actual attribute names.

### External database

Selecting the **External database** option will instruct JMap to display information taken from another database, instead of the layer. This option allows you to query any database that has a field corresponding to one of the layer's attributes.

Attributes	
Database	Select the database from which the report data will be extracted. The database to query must have been configured in JMap Admin beforehand.
SQL query	Enter the SELECT SQL query that will be used to extract the data from the database. This query can have several tables. The query must include the key field used to join with a layer attribute.  Afterwards, you must click on <b>Execute</b> in order to execute the query once.

Join fields	
Table	Select the table containing the join field.
Field	Among the fields in the selected table, select the field that will be used to join with the layer.
Attributes	Select the layer attribute that will be used to join with the data from the database.

### Captions

For reports that take their data from an external database, you can define the names of the fields to be displayed in the report, instead of using the field names in the database. Click on **Captions** to define these field names.

## Forms

In JMap, forms are used for attribute queries to enter the search parameters, to enter attribute values of editable layers and to manage data stored in databases. This is always done in relation with the elements of a layer. A type of form called a subform can also be accessed from another form.

The JMap administrator designs the forms using the form designer. Afterwards, users can use them in JMap Pro, JMap Web, and JMap Mobile. Depending on access privileges, users can use data entry forms to view, add, modify or delete data.

To enter the attributes of a layer's elements, JMap generates a default form if none has been created. This simple form shows all available attributes. In general, it is much more convenient to create a form adapted to your needs.

The following sections explain the form creation process in detail and the functionality of each type of form.

The image displays two overlapping windows titled 'Attributes'. The top window is in the 'Information' tab and contains the following fields:

- Number of railways: 2
- Average number of trains pe...: 34
- Speed permitted on railw...: 20 Km/h
- Crossing angle: 15 Degrés (°)
- Warning system: Mechanical
- Signals: (empty dropdown)
- Whistling:
- Photo: (image of a railway crossing) with an 'Add' button below it.

The bottom window is in the 'Inspections' tab and features a table with the following data:

Date d'inspection	Inspecté par	Observations
Tue Apr 04 00:00:00 EDT 20...	MrA	Good

Below the table are buttons for 'Add', 'Edit ...', and 'Delete'. At the bottom of the window are 'Cancel' and 'OK' buttons.

Examples of forms displayed in JMap Pro

## Form Designer


The interface of the form designer allows you to define the content and layout of the forms used to enter attributes and perform queries.

Forms are organized in a grid, and you can configure the number of rows and columns. Columns and rows can be added to the grid at any moment. All empty rows at the bottom of the form and empty columns at the right of the form will be automatically eliminated when the form is saved.





Each cell of the grid can contain a component of the form (label, text entry field, value list, etc.) but each component can also span several cells horizontally.

Each form can have one or more sections. The user can move from one section to another within a form. This can be especially useful if the form is long or complex.





The following image shows the main parts of the form designer.



*Form designer interface*

- 1 Drag a component to a cell in the form. All available cells are highlighted.
- 2 Click on  to create a new section, to delete an existing section or to rename a section.  
Click on  to reset the entire form.
- 3 These tabs allow you to access the different sections.
- 4 Click on the  and  buttons to insert empty rows or columns where required.




- 5 The  symbol indicates that the component is in read-only mode.
- 6 The  symbol indicates a required field.
- 7 The  button allows you to modify the component's parameters. The  button allows you to remove the component from the form.


Most form components must be associated with either a layer attribute, a database field or a search criterion, depending on the type of form created. The Label, Photo, and Group components are exceptions to this rule.

## Component settings

Each type of component has its own configuration window. The settings allow you to control the behavior and appearance of the component. The following table describes some of the settings that are common to several components. A comprehensive description of available components is provided further below.


Form component settings	
Attribute	Select the layer attribute or the query variable to which this component is associated. This is the attribute or variable that the form component will provide.
Required	Determines if this is a required field. The user cannot submit the form until all required fields have been populated. To make a field optional, you must unselect this option. Required fields are identified with a  in the form designer.
Read only	Select this option to make this a read-only component. The user will not be able to modify the content. This option should be used to modify a component with a default value.
Column span	By default, each component occupies only one cell. For a component that spans several cells horizontally, enter the number of cells the component will span. Cells occupied by a spanned component are labeled Spanned.
Tooltip	This text is displayed in a tooltip when the user places the mouse pointer on this component.
Label (prefix)	Enter static text that will appear above the component.
Label (suffix)	Enter static text that will appear on the right of the component.


Width (pixels)	Specify the width in pixels of the component entry field, excluding the suffix label. The default value is 100. The width of each column of the form will automatically be the same as the widest component in the form.
Default value	Optionally enter a default value to initialize the data entry field. You can use certain <a href="#">functions</a> to initialize the default value of a component.



An example of the layout of a form's components

The following table describes the various components available to create forms and their specific settings. Note that some components are not available to create attribute queries.

Form components	
<b>Aa</b> Label	Static text to be displayed in the form. The text's alignment (left, right, center) can be specified, along with the font style used to display the text. Certain <a href="#">functions</a> can be used in the label text.
 Text	A field used to enter an alphanumeric value. The associated field must be alphanumeric or numeric.  <b>Input mask:</b> An input mask can be used to control the format of the value entered.  <b>Multiline:</b> (alphanumeric fields only) If this option is enabled, the entry field will cover several lines of text, making it easier to enter longer text.  <b>Max. number of characters:</b> (alphanumeric fields only) Determines the maximum length of the text a user can enter. This must comply with the restrictions of the database field containing the data.

	<p><b>Range validation: (numeric fields only):</b> Allows you to define a range of accepted values (e.g. from 0 to 100).</p>																				
<p> List (single choice)</p>	<p>A list of values from which only one value can be selected. The associated field must be numeric or alphanumeric. The values in the list can be provided in several different languages if your project supports multiple languages.</p> <p>The list can be dynamic, which means its content can be modified dynamically based on the selection of a value from another list. For instance, when selecting a country in a list, another list will be refreshed dynamically to display only the cities of the selected country.</p> <p><b>Parent attribute</b></p> <p>If the list must be dynamic, select the parent attribute.</p> <p>In order to link list B (child) to a list A (parent), you must begin by selecting the parent attribute for list B (the attribute associated to list A). If there is a change in the value selected in list A, the content of list B will be updated. The values of list B are determined by the relationship between its values and the values of the parent attribute. If list B has only one value, it is selected automatically.</p> <p>The values in the list can be entered manually or they can be taken from a database or another source:</p> <p><b>Values</b></p> <p>Enter the values in the space provided, indicating, for each one, the parent value (only if the list is dynamic), the value to use in the database and the label to display in the list. This value will be used as the data. The label is only used for the information the user will see. If the value and the label are the same, enter the same value twice. If the list is not dynamic, leave the parent value blank.</p> <p><b>Get values from a database</b></p> <p>You must select the database from which you wish to obtain the values. Afterwards, enter an SQL query that will be executed to obtain the parent values (only if the list is dynamic), the values, and the labels to be displayed. Normally, labels must be unique and sorted.</p> <p>The following examples use the MY_TABLE table.</p> <table border="1" data-bbox="537 1656 1455 1822"> <thead> <tr> <th>ITEM_TYPE</th> <th>PARENT_VALUE</th> <th>ITEM_VALUE</th> <th>ITEM_LABEL_EN</th> <th>ITEM_LABEL_FR</th> </tr> </thead> <tbody> <tr> <td>Country</td> <td>NULL</td> <td>CAN</td> <td>Canada</td> <td>Canada</td> </tr> <tr> <td>Country</td> <td>NULL</td> <td>US</td> <td>United States</td> <td>États-Unis</td> </tr> <tr> <td>City</td> <td>CAN</td> <td>TOR</td> <td>Toronto</td> <td>Toronto</td> </tr> </tbody> </table>	ITEM_TYPE	PARENT_VALUE	ITEM_VALUE	ITEM_LABEL_EN	ITEM_LABEL_FR	Country	NULL	CAN	Canada	Canada	Country	NULL	US	United States	États-Unis	City	CAN	TOR	Toronto	Toronto
ITEM_TYPE	PARENT_VALUE	ITEM_VALUE	ITEM_LABEL_EN	ITEM_LABEL_FR																	
Country	NULL	CAN	Canada	Canada																	
Country	NULL	US	United States	États-Unis																	
City	CAN	TOR	Toronto	Toronto																	

City	CAN	MTL	Montreal	Montréal
City	USA	NY	New York	New York
City	USA	LA	Los Angeles	Los Angeles
City	USA	MIA	Miami	Miami

**Example:** List of countries, available in English and in French. This list is not dynamic. It is associated with a COUNTRY attribute.

```
select * from MY_TABLE where ITEM_TYPE = 'Country' order by
ITEM_VALUE;
```

In this example, the ITEM\_VALUE field contains the value, the ITEM\_LABEL\_EN field contains the name of the country in English, and the ITEM\_LABEL\_FR field contains the name of the country in French. There is no parent value because the list is not dynamic (it does not have a parent list).

**Example:** List of cities, available in English and in French. This list is dynamic. Its parent attribute is COUNTRY, which is associated with the previous list. It lists the cities for the country selected in the parent list.

```
select * from MY_TABLE where ITEM_TYPE = 'City' order by
ITEM_VALUE;
```

In this example, the ITEM\_VALUE field contains the value, the ITEM\_LABEL\_EN field contains the name of the city in English, and the ITEM\_LABEL\_FR field contains the name of the city in French. The PARENT\_VALUE field contains the parent value.

**Important:** The SQL query of a child list must include the field that allows you to establish the relation with the parent values. The previous example used *select \** to include all the fields in the queries.

**Note:** At times, values to be displayed in a list come from a table associated to a spatial data source stored in JMap Server's System database. In such a case, the name of the physical table cannot be known. To solve this, you can use this simple approach: instead of entering the name of the table, enter the name of the data source between dollar signs (\$).

Example:

```
select distinct ID_CITY, CITY from $World
cities$ order by CITY
```

**Provider**





	<p>Other sources may be available to provide the values and labels. If this is the case, you can select this option and choose the source in the list of available sources.</p>
 <p>List (multiple choices)</p>	<p>A value list from which one or more values can be selected. The associated field must be alphanumeric. The value saved in the field is the list of selected options, separated by commas (,).</p> <p>The values in the list can be entered manually or they can come from a database or another source. Refer to <b>List (single choice)</b> for more information.</p>
 <p>Check box (true or false)</p>	<p>Populates the associated field for which there are only 2 possible values. The 2 possible values must be specified and be character strings (e.g. true or false) or numerical values (e.g. 0 or 1). If the associated field is boolean, you must use true and false.</p> <p><b>Checked value:</b> Value to be recorded if the check box is selected.</p> <p><b>Unchecked value:</b> Value to be recorded if the check box is not selected.</p>
 <p>Calendar (single date)</p>	<p>Allows you to select a date. The layer attribute or the field used for the query must be of one of the following types: date, datetime or timestamp.</p> <p><b>Date format:</b> This is the format that the calendar component will use to display the selected date. If the user enters the date manually, he or she must also use this format (e.g. dd/MM/yyyy, yy/MM/dd H:ss, etc.).</p>
 <p>Photo (unavailable for attribute query forms)</p>	<p>This component allows the user to insert images in a form. In JMap Mobile, it allows the user to take photos with the device's integrated camera. In JMap Pro or JMap Web, the user can select existing images to insert in the form. This component cannot be present more than once in the same form.</p> <p>For a layer attributes form, the photos can be stored in the <b>JMap Server System database</b> (in this case, no configuration is required) or in an <b>external database</b>. When this component is added to a database form, the photos must be stored in an external database. You must then define all required parameters for storing the photos.</p> <p><b>Storage:</b> Choose the <b>JMap</b> option to store the photos in JMap's System database (only available for layer attribute forms). Photos selected by the users are copied in the <code>JMAP_HOME\db\documents</code> directory, and the relation between the layer element and the photo is added to the <code>JMAP_DOCUMENTS</code> table in the System database.</p> <p>Choose the <b>External</b> option to store the photos in the database or in the directory of your choice. The relation between the layer element and the</p>

photo is stored in the table and database of your choice. If you select **External**, you must define the entire configuration that follows.

**Delete photos with elements:** Select this option if you want the photos associated with an element to be deleted automatically if the element is deleted. This option is not enabled by default.

**Database:** Select the database where the photos must be stored. This database must be configured beforehand in JMap Admin.

**Table:** Select the table that will contain the information on the photos. This table must have the following structure. The name of the table and fields may vary.

MY_PHOTOS	
ID_PHOTO	INT
ID_ELEMENT	VARCHAR
FILE_PATH	VARCHAR
PHOTO	BLOB

The BLOB field is not required if the photos are stored on the drive and not in the database. Refer to the **Photos persistence** option for more details.

**Photo ID field:** Select the field in the table that will contain the photo's unique numerical identifier.

**Element ID field:** Select the field in the table that will contain the attribute identifying the layer element. This attribute is called the key attribute and it is selected when the spatial data source associated with the layer is created.

**File name field:** Select the field in the table that will contain the name of the file for the photos.

**Photos persistence:** Choose the **Database** option to save the photos directly in the database, in a BLOB field existing in the table. You must then select the BLOB field. Choose the **Disk** option to save the photos in a folder of the server's file system. You must then enter the **photos folder** that will contain the photo files.



Tree (tree of values)

This component displays a value tree structure with N levels. The user can select a value in the tree, leaf or branch. This value will be stored in the associated attribute. The associated attribute must be alphanumeric.

The values of the tree can be provided in several languages if your project supports multiple languages.

The tree shows a parent-child data structure, like the dynamic lists that are linked to one another. However, unlike dynamic lists, the tree is associated to just one attribute.

The tree's values can be entered manually or they may come from a database or another source:

### Values

Enter the values in the space provided as you build the tree structure. For each value entered, you can define the parent (or the root of the tree)

### Get values from a database

You must select the database from which you wish to obtain the values. Afterwards, enter an SQL query that will be executed to get the values from a table with a parent-child relationship.

The following example uses the MY\_TABLE table.



ITEM_TYPE	PARENT_VALUE	ITEM_VALUE	ITEM_LABEL_EN	ITEM_LABEL_FR
Country	NULL	CAN	Canada	Canada
Country	NULL	US	United States	États-Unis
City	CAN	TOR	Toronto	Toronto
City	CAN	MTL	Montreal	Montréal
City	USA	NY	New York	New York
City	USA	LA	Los Angeles	Los Angeles
City	USA	MIA	Miami	Miami

**Example:** Tree containing countries (level 1) and cities (level 2), available in English and French.

```
select * from MY_TABLE;
```

In this example, the ITEM\_VALUE field contains the value, the ITEM\_LABEL\_EN field contains the name of the country or city in English, and the ITEM\_LABEL\_FR field contains the name of the country or city in French. The PARENT\_VALUE field contains the parent. With this configuration, JMap will build the following tree:

Canada

	<p>Montreal</p> <p>Toronto</p> <p>United States</p> <p>Los Angeles</p> <p>Miami</p> <p>New York</p>
 <p>Table</p> <p>(unavailable for attribute query forms)</p>	<p>Allows you to manage data originating from databases external to JMap and for which a 1 to N relationship exists with the layer elements.</p> <p>Example:</p> <p>Suppose a points layer represents fire hydrants in JMap, and a database external to JMap contains data on the inspections performed on these fire hydrants. For each fire hydrant, 0, 1 or several inspections can be performed. In the attributes form of the fire hydrants layer, the table allows you to display inspection data regarding a fire hydrant, where each line in the table represents an inspection. Depending on the permissions configured, the table can also be used to add, modify or delete the inspection data.</p> <p>The table is always associated with a subform. This subform defines how external data is accessed and allows this data to be entered. <b>The subform must be created before the table can be configured.</b></p> <p>The table parameters allow you to define the external data fields that will be displayed in the table and their order of appearance.</p> <p><b>Subform:</b> Select an existing subform that will be used to populate the values associated with the table.</p> <p><b>Fields:</b> Allows you to manage the fields displayed in the table. These are the fields of the subform associated with the table. You can modify the field names, their display order, and their visibility in the table.</p> <p>For more information on using external data with JMap forms, refer to the <a href="#">Database Forms</a> section.</p>
 <p>Group (groups components together)</p>	<p>This component is used to group form components together. A frame with a title will be drawn around the components belonging to the same group. Insert this component in the cell of an empty row to start a new group. This component automatically spans all cells of the row. It cannot be inserted on a row that already has other components.</p>

The following functions can be used to initialize form components.

## Functions



username()	Replaced by the user's code.
fullname()	Replaced by the user's full name.
date()	Replaced by the current date.
datetime()	Replaced by the current date and time.

## Layer Attributes Forms


These forms are used to enter the attribute values of an editable layer. Only one attribute entry form can exist per layer. The user must have the required permissions to modify the values of a layer's attributes. Refer to the [Layer Permissions](#) section for more information.

### Creating a layer attributes form

To create a form that will be used to enter a layer's attributes, select **Forms** in the layer's settings menu, then click on **Create**.

Enter a name for the new form. You must then select the type of form to create, **Layer attributes**. Click on **Save**.

Afterwards, select **Form layout** in the settings menu to go to the form designer and add components. Each component of the form must be associated with an attribute of the layer. The component provides the attribute value, and the value is updated when the user closes the form and saves the changes. Refer to the [Form Designer](#) section for more information.



*The layer attributes form is used to manage only the attributes that are available in the spatial data source and bound to the layer.*


## Database Forms

Database forms are used to manage data stored in databases that are external to JMap. They allow you to add new data as well as modify or delete existing data. You can create several database forms for one layer. Each database form has its own permissions to control which users can make changes to the data.

These forms can be used to manage data using a **1 to 1** relationship with a layer's data. In this case, a record is added when an element is created, and this record is usually deleted when the element is deleted.

They can also be used to manage data using a **1 to N** relationship with the layer data. In this case, a special type of form called a subform is used and is always associated with a table form component. Refer to the [subforms](#) section for more information on this topic.

Configuring this type of form is an advanced JMap function that requires writing SQL queries to extract, add, modify and delete data.



*Database forms use a common field to manage data external to JMap that is related to the layer.*

## Creating a database form

To create a database form, select **Forms** in the layer parameters menu. Make sure you open the **Forms** tab, then click on **Create**.

You must enter a name for the new form. Afterwards, you must select the type of form to create, **Database**, then select the database containing the data to be used in the forms.

At the following step, a window allows you to enter the form's SQL queries. These queries are used to extract, add, modify, and delete data. The **SELECT** query is required, but the others are optional. Only operations for which SQL queries have been provided can be performed.

A special syntax is used for SQL query configuration. In general, each line of this syntax must end with a semicolon (;). The syntax is not case sensitive.

The following table provides a detailed explanation of how this syntax works.

Syntax for database forms	
<b>ev(attrib)</b> or <b>elementValue(attrib)</b>	<p>This function returns the value of the attribute specified as a parameter for an element.</p> <p><b>Example:</b> <code>ev(city);</code></p> <p>(Returns the value of the element's city attribute.).</p>
<b>fv(field)</b> or <b>formValue(field)</b>	<p>This function returns the value in the form for the field specified as a parameter. The name of the table must be the prefix of the field name.</p> <p><b>Example:</b> <code>fv(table.name);</code></p> <p>(Returns the value entered in the form component associated with the table.name field of the database.).</p>
<b>ei()</b> or <b>elementId()</b>	<p>This function returns the id of the element. It can be the <code>jmap_id</code> field, or another field, as configured in the spatial data source.</p>
<b>\$variable</b>	<p>Allows you to create and initialize variables that can be used in the various expressions. For the <b>INSERT</b> query of a form, a variable containing the unique identifier of the inserted record must be used.</p> <p><b>Example:</b> <code>\$city = EV(city);</code></p> <p>(Creates a <code>\$city</code> variable initialized with the value of the element's city attribute.).</p>
<b>nti(table, field)</b> or <b>nextTableId(table, field)</b>	<p>This function returns the next value to use as a numeric identifier for the table and field specified as parameters. The specified field must exist in the specified table and must be an integer field. The function determines the maximum value existing in the table and returns this value incremented by 1 (<code>max + 1</code>). This function is useful when adding a new record in the database when the table has a unique identifier.</p> <p><b>Example:</b> <code>\$sid = nextTableId(inspections, inspection_id)</code></p> <p>(Creates and initializes a <code>\$sid</code> variable with the value of the next <code>inspection_id</code> identifier in the inspections table. If the maximum value present is 100, the value returned is 101).</p>

The following table provides a detailed explanation of each parameter in the database form creation window.

### Form properties

Database	Select the database containing the data that must be managed by the form.
SELECT query	<p>SQL query that provides the data to populate the form's fields. All fields returned by this query can be used to configure form components and also within the other queries defined in the form using the fv() function.</p> <p>The query must have a condition to link a layer attribute with a database field.</p> <p><b>Example:</b> <code>select * from assets where asset_id = ev(asset_id);</code></p> <p>In this example, all the fields of the assets table are obtained and available to configure form components. The asset_id field is used to link towards the layer element using the ev(attrib) function.</p>
Field of the unique identifier	The SELECT query must include a unique identifier field (numeric or alphanumeric). Select the field that must be used as a unique identifier.
INSERT query	<p>SQL query used to insert new data in the database. You should only configure this query if the form must allow records to be added to the database. You must define a variable that contains the value of the unique identifier for the new record.</p> <p><b>Example:</b> <code>\$id = ev(asset_id);</code></p> <p><code>insert into assets (asset_id, date_inst, asset_type) values (\$id, fv(assets.date_inst), fv(assets.asset_type));</code></p> <p>In this example, a \$id variable is created and initialized with the map element's asset_id attribute value using the ev(attrib) function. The form data is inserted in the assets table when the insert SQL query is executed. The values of the assets.date_inst and assets.asset_type fields are provided by the values the user has entered in the form using the fv(field) function. The value of the asset_id field is provided by the \$id variable.</p> <p><b>Example:</b> <code>\$id = nti(inspections, id);</code></p> <p><code>insert into inspections (id, date_insp, insp_by, notes) values (\$id, fv(inspections.date_insp), fv(inspections.insp_by), fv(inspections.notes));</code></p> <p>In this example, a \$id variable is created and initialized with the next value (max + 1) of the id field from the inspections table. The form data is inserted in the inspections table when the INSERT SQL query is executed. The values of the date_insp, insp_by and notes fields are provided by the values the user has entered in the form using the fv(field) function. The value of the id field is provided by the \$id variable.</p>
Variable with the ID of the new element ()	Select the variable containing the value of the unique identifier of the new record inserted in the table. It must be defined with the INSERT query.


UPDATE query	<p>This SQL query updates the data in the database. You should only configure this query if the form must allow data to be updated.</p> <p><b>Example:</b> update assets set date_inst = fv(assets.date_inst), asset_type = fv(assets.asset_type) where asset_id = ei();</p> <p>In this example, the form data is used to update the assets table when the UPDATE SQL query is executed. The values of the assets.date_inst and assets.asset_type fields are provided by the values the user enters in the form using the fv(field) function. The WHERE clause allows you to update the record containing the element's unique identifier using the ei() function.</p> <p><b>Example:</b> update inspections set notes = fv(inspections.notes) where inspection_id = fv(inspections.inspection_id);</p> <p>In this example, the form data is used to update the inspections table when the UPDATE SQL query is launched. Only the value of the notes field is updated and it is provided by the value the user enters in the form using the fv(field) function. The WHERE clause uses the fv(field) function to obtain the value of the record's unique identifier. Note that in this case, the inspection_id field is not associated with a form component, however, its value is still accessible through the fv(field) function.</p>
DELETE query	<p>This SQL query deletes the data from the database. You should only configure this query if the form must allow data to be deleted.</p> <p><b>Example:</b> delete from assets where asset_id = ev(asset_id);</p> <p>In this example, the record corresponding to the element's asset_id attribute value is deleted from the table using the ev(attrib) function to obtain the value of the element identifier.</p> <p><b>Example:</b> delete from inspections where inspection_id = fv(inspections.inspection_id);</p> <p>In this example, the record corresponding to the inspection's unique identifier is deleted from the table using the fv(field) function to get the value of the identifier.</p>

## Creating a subform

Subforms are database forms that are opened from a **Table** component that exists in another form. They are normally used to manage data that has a **1 to N** relationship with the layer's elements. They could be used to manage data for inspections on assets (N inspections can be associated to the same object), for example. They are configured similarly to the other database forms.

To create a subform, select **Forms** in the layer parameters menu. Make sure you open the **Subform** tab, then click on **Create**. You must enter a name for the new form and select the database containing the data to be used in the forms.

At the following step, you must configure the SQL queries of the subform, as explained above for the creation of a database form.



*Subforms are database forms that use a common field to manage data with a 1 to N relationship with the layer data.*

## Permissions of database forms

Database forms have their own permissions. Available permissions are described in the table below.

Form permissions	
Add data	Allows a user or group to use the form to add new data in the database.
Modify data	Allows a user or group to use the form to modify existing data in the database.
Delete data	Allows a user or group to use the form to delete data existing in the database.

## Attribute Query Forms

Like data editing forms, attribute query forms are created using the form designer. They allow the users to enter query parameters. Each form component is therefore associated with a parameter of the query (\$param1, \$param2, etc.).

Unlike the other types of forms, they cannot be divided into sections. In addition, the **Photo** components are not available for this type of form.

These forms are created when configuring attribute queries, by clicking on **Form layout**.

When creating an attribute query form, it is important to consider which parameters are required and which are optional in the query definition. For instance, if **Required** is not selected for a form component, the query must consider this parameter as optional. Refer to the [Creating attribute queries](#) section for more information on optional parameters in queries.

## JMap Extensions

JMap standard features can be extended to provide new specialized functions. This is done using JMap extensions. A JMap extension is an optional module that can be plugged into JMap Server and/or JMap applications in order to provide the desired set of new functions. Some JMap extensions already exist and are available as separate products, and some others will be available in the future. Organizations can also develop their own extensions using the JMap SDK.

The **Extensions** section in JMap Admin shows the list of existing extensions of each type. The extension types are Server, Client, Mobile, and Web.

### Server extensions

JMap Server extensions add new functionality on the server side. They can include their own configuration interfaces, which are integrated to JMap Admin. Simply click on the name of a server extension to access its configuration interface.

Server extensions can be enabled or disabled by clicking on the **Enable** and **Disable** buttons. Disabled extensions are inactive and cannot process requests. Extensions can also be reinitialized by pressing the **Reinitialize** button. In this case, they are stopped and restarted, which can be useful if an extension must read configuration files that have been modified, for instance.

### Client extensions

JMap Client extensions add functionality to JMap Pro applications. Generally, an extension adds a new toolbar or new menu items to an application. Using the application deployment tool, you can select the extensions that will be included in a JMap Pro application. Refer to the [Deploying JMap Pro Applications](#) section for more details on this topic. JMap Client extensions are presented in this section for information purposes only.

### Mobile extensions

JMap Mobile extensions add functionality to JMap Mobile applications. JMap Mobile extensions are presented in this section for information purposes only.

### Web extensions

JMap Web extensions add functionality to JMap Web applications. JMap Web extensions are presented in this section for information purposes only.

### Extension permissions

#### Administrator permissions

The administrator permissions of JMap Server extensions define the extension's administration rights for users authorized to use JMap Admin. Client, Web, and Mobile extensions are not affected



by permissions. For more information on concepts related to permissions and administration roles in JMap Admin, refer to the [Managing Permissions](#) section.

<b>Permissions</b>	
Administrate extension	Allows an administrator to access the extension's configuration sections and modify the settings.

## Deploying JMap Applications

Deploying a JMap application consists of preparing the application and placing it online to be accessed by users. You must select the desired options (application type, activated extensions, access controls, etc.) to customize the application according to your needs. In order to allow a user to open a deployed JMap application, simply give the user the application URL.

Deployed JMap applications are placed online in the web server integrated to JMap Server. They can also be copied manually to other web servers.

The deployment section displays a list of applications that have already been deployed.

### Creating a new deployment

To create a new application deployment, click on the **Create** button in the **Deployed applications** section. Some parameters will be common to all types of applications. The following tables describe these parameters.

Template	
Application type	<p>There are 5 types of JMap applications. Each type of application has different features that are adapted to different needs. Custom application templates can also be added; these can be variants of the types offered by default.</p> <p><b>JMap Pro applications:</b> This type of JMap application offers advanced functionality. It requires more IT resources, and a Java Runtime Environment (JRE) must be installed (Java is no longer required if you use the new deployment mode with an installation program).</p> <p><b>JMap Web applications:</b> This type of JMap application is lighter and you can run it from a web browser or a mobile web browser. It doesn't offer as many advanced features as JMap Pro applications.</p> <p><b>JMap Mobile applications:</b> This type of application is compatible with iOS, Android, and Windows mobile devices. It allows users in the field to enter data using forms. JMap Mobile supports GPS, camera and local storage functions for working in offline mode. This type of deployment prepares the service to support JMap Mobile. The JMap Mobile application must be installed from one of the various app stores. <b>This type of application is replaced by JMap Survey, which connects directly to projects, without the need to create a deployment.</b></p> <p><b>WFS Service:</b> This type of application is a vector data web service destined to provide data to third-party applications through the Web Feature Service standard protocol.</p>

	<b>WMS Service:</b> This type of application is a web service for the production of map images. It is destined to provide maps to third-party applications using the Web Mapping Service standard protocol.
--	---

Identification	
Name	Enter a name for the new deployed application. Names must be unique. The name can contain spaces and any other characters.
Type	Select the deployment type, either local or external.  <b>Local:</b> The application service will be deployed directly in JMap Server.  <b>External:</b> Select this option for applications that must be deployed on a web server that is external to JMap Server. The application service will not be deployed in JMap Server. Instead, a .war file will be created. This file must be copied onto the external web server. A Download button in the deployment section allows you to download the .war file.
Protocol	The protocol to be used for communication between the JMap application and JMap Server. Select https for secure communication. If the HTTPS protocol is not configured in JMap Server, this option is not available. For more information on using the HTTPS protocol, refer to the <a href="#">Using HTTPS with JMap</a> section.
Application host	The host name or IP address that will be included in the URL of the deployed application. If your server has several IP addresses, specify the one that must be used. If you have selected the <b>External</b> deployment type, make sure you enter the name or address of the external web server where the application will be deployed.
Application port	The TCP/IP port used in the URL of the deployed application.
Relative path	The path used in the URL of the deployed application, taken from the name given to the application.

The following steps depend on the type of application you selected. Refer to the following sections: [JMap Pro Applications](#), [JMap Web Applications](#), [JMap Mobile Applications](#) and [WFS and WMS Services](#).


## JMap Pro Applications

The following settings apply to JMap Pro applications.

Application options	
Project	Select the project to open when JMap Pro is started.
Language	<p>Select the language to use in JMap Pro.</p> <p>The elements of the graphical interface (menus, buttons, text in windows, etc.) will be in the selected language. If you select the Automatic option, the language of the graphical interface will be the same as the language defined in the regional options of the user's system. If the aforementioned language is not supported by JMap, the language of the interface will be set to English.</p> <p>The project configuration (names of layers, mouseover bubbles, etc.) will be in the selected language, provided translations into this language are available in the project. If you select the Automatic option, the language of the project will be the same as the language defined in the regional options of the user's system. If the user's system language is not available in the project, the default language defined in the project will be used.</p>
Map rotation	You can define the rotation to be applied to the map when opening the application.
Controlled access	This option allows you to determine if access to this application must be controlled. If this option is activated, an authentication window will appear when the application is launched. If this option is not selected, the project must allow anonymous sessions.
Enable single sign-on	Select this option to activate single sign-on for this application. Note that single sign-on must be configured on JMap Server for this option to be available. When JMap Pro is started, if single sign-on cannot work, an authentication window will be automatically displayed. Refer to the <a href="#">Single Sign-On</a> section for more information.
Embedded in the browser	<p>Select this option to integrate the JMap application in a web browser window as a Java applet. Otherwise, the application will open in its own window.</p> <p><b>Note:</b> This option is not recommended because Java execution is no longer supported by most web browsers.</p>

<b>Advanced</b>	
Connection type	Select the connection method to be used between the client application and JMap Server. Direct connections are usually appropriate for internal use; proxy connections are destined to users outside the local network. Proxy connections use the HTTP protocol and therefore can go through firewalls more easily.
Max. memory for data	Select the maximum amount of memory that can be used to store vector data in the client application. When this limit is reached, the application will free up memory by deleting old data in order to store new data. The default value of 128 MB is appropriate for most sets of data but you may have to adjust it when you have a large amount of data to display.
Max. Heap size	Select the maximum amount of memory that can be assigned to the application to store all the settings and data needed to run it. This memory includes the memory previously configured for vector data. This amount of memory should always be higher than the maximum memory for data. The default value of 512 MB is suitable for most applications, but you may have to adjust it in some cases. Note that the amount of memory used by the application process (as seen in task managers) can exceed this value.
Display this message in login window	You can optionally add a message that will be displayed in the login window to all of the application's users.
Display projects list in login window	Select this option to display a list of available projects in the connection window. Users can then choose the project they wish to open. The project's security settings will be used to determine whether or not a user is authorized to open a particular project.
Do not list users	Select this option to hide the list of users in the deployed application. This application can be useful if you must hide the accounts of internal users when you deploy an application that is accessible to the general public via the Internet. The users list serves various purposes, such as sharing contexts and sending maps by email.
Parent path of .jmap folder	This advanced setting allows you to specify a different location than the default for the .jmap folder. This folder contains JMap Pro settings and cached data.  Specify the desired location of the .jmap folder.  Example: C:/permanent_folder  Will give you this final folder: C:/permanent_folder/username/.jmap

<b>Map options</b>	
Show map overview by default	Select this option to display the overview window when the application opens.
Display scalebar	Select this option to display a graphic scalebar in each application map. The user can add or remove the bar during his/her session.
North arrow	Select this option to display a graphical arrow pointing north in every map of the application. The user can add or remove the arrow during his/her session. You can decide which model you wish to use, its size, and where it will be positioned on the map.

Click on  to add a logo that will be displayed on the map.

<b>Logos</b>	
Position	Defines the position of the logo on the map.
Offset X	Defines a horizontal offset value in relation to the selected position.
Offset Y	Defines a vertical offset value in relation to the selected position.
Transparency	Indicate the partial transparency of the logo (0% = opaque, 100% = invisible).

<b>Extensions</b>	
Name of extension and version	Extensions available for JMap Pro applications are indicated here. Select the ones you wish to deploy with the application. Extensions will usually add new windows, menus or toolbar to the application.
Toolbar visible	Select this option to make the toolbar of the selected extension visible when the application starts up. Otherwise, the user can display the toolbar on request.
GUI visible	Select this option to display the windows and other components of the selected extension's graphical interface when the application starts up. Otherwise, the user can display them on request.
Extra parameters	Some extensions can take entry parameters when the application starts up. If this is the case, these parameters can be inserted in this field for

	the selected extension.
--	-------------------------

Click on **Finish** to complete the deployment process.

## JMap Web Applications

The following settings apply to JMap Web applications.

Application options	
Project	Select the project to open when JMap Web is started.
Language	<p>Select the language to be used in JMap Web.</p> <p>The elements of the graphical interface (menus, buttons, text in windows, etc.) will be in the selected language. If you select the <b>Automatic</b> option, the language of the graphical interface will be the same as the language defined in the regional options of the user's system. If the aforementioned language is not supported by JMap, the language will be set to English.</p> <p>The project configuration (names of layers, mouseover bubbles, etc.) will be in the selected language, provided translations into this language are available in the project. If you select the <b>Automatic</b> option, the language of the project will be the same as the language defined in the regional options of the user's system. If the user's system language is not available in the project, the default language defined in the project will be used.</p>
Map rotation	You can define the rotation to be applied to the map when opening the application.
Controlled access	This option determines if access to this application must be controlled. If this option is activated, an authentication window will display at application startup. If this option is not selected, the project must allow anonymous sessions.
Docked layers panel at startup	Determines if the sidebar (containing the list of layers and searches) will be displayed when the application opens.
Continuous zoom	This option allows you to zoom continuously on the map. If this option is not selected, the zooms are made in predetermined increments. This option is automatically disabled if Google Maps is displayed as a base

	map. This option is selected by default for new web deployments from JMap 7 Cairo.
Geolocation tool	Select this option to activate the geolocation tool in the application. The option will only be available if the application is deployed with the HTTPS protocol. If this option is not selected, the geolocation button will be absent from the user interface.
Data editing tools	Select this option to activate the data editing tools for element geometries and their attributes. Even if these tools are activated, the user must have the necessary permissions to modify the data of a layer.
Selection tools	Select this option to activate the selection tools in the application. If this option is not selected, the selection button will be absent from the user interface.
Google tools	Select this option to activate the address search, directions, and Street View from Google.  Important: You must make sure you use this option in accordance with Google's license agreement.
Sharing tools	Select this option to enable sharing tools (link to this map, integrated map, create an image). If this option is disabled, the sharing menu will not appear in the user interface.
Share on social networks	If the sharing tools option is selected, you can select this option to enable map sharing on social networks (Facebook, LinkedIn, Twitter).

### GeoWebCache

Username	If you are using a GeoWebCache server, enter the user account that GeoWebCache must use to access the deployed application and selected project. It is absolutely necessary that this user account have the appropriate permissions to open the project associated with this deployed application. Refer to the <a href="#">Using a GeoWebCache Server</a> section for more information.
Password	Enter the password that GeoWebCache must use to access the deployed application and associated project.

### Advanced



Cross-Origin Request Sharing	Select this option if JMap Web needs to be embedded in a website whose domain name (DNS) is different from that of the application.
X-Frame Options	This field offers a range of options for the JMap Web application to be called from an iframe.
X-Frame Authorized Referers	In this field, add any domain URL authorized to call the JMap Web application in an iframe. URLs must be separated by semicolons. For example: <code>http://172.17.101.14:8082;http://172.17.101.15:8083</code> .
Session timeout	Check this option to log the user out after a given period of inactivity.
REST API Address	JMap Web requires JMap Server's REST services. Enter a different address for the REST services if they were deployed on another server.

## Configuring layers

This type of application requires a layer configuration that may differ from the configuration existing in the project to be disseminated. JMap Web displays map images that are generated by JMap Server from the project layers. An image will often contain the data of several layers combined together.


### Tiled image layers

The images produced can either be tiled (images with fixed sizes) or not tiled (images with variable sizes). In the case of tiled images, they can be generated in advance or on demand, and they can be cached to improve performance. Images that are not tiled are always generated on demand. In general, tiled image layers offer better performances and a smoother user experience, but they may add border effects and overload the server if there are a lot of them.

### Base layers


Base layers are used to display a map in the background. The data of base layers is static and cannot be queried by JMap. Only one base layer can be displayed at a time in the application, but if several are available, the user can select one.


Base layers can be made up of layers from the JMap project or they may come from external sources (OpenStreetMap, Google Maps, Bing Maps). When they are produced by JMap Server, tiled, and cached, they can be shared by several JMap Web applications.

To add a layer, click on .

### Types of layers

<p>JMap dynamic layer</p>	<p>Dynamic layers can be tiled or not tiled, but they are always generated on demand and they cannot be cached. They are a good option for data that changes often or that requires more interactivity. The user can control the visibility of each layer composing the dynamic layer. Users can also display thematics and their legends, edit data, make selections, etc.</p> <div data-bbox="630 541 1344 884" data-label="Image"> <p>The screenshot shows a user interface for a dynamic layer. At the top, there is a header 'Dynamic Layer' with a dropdown arrow and a checked checkbox. Below it, a list of layers is shown: 'Parking' with a checked checkbox and a blue 'P' icon; 'Emergency' with a checked checkbox and a multi-colored dot icon; 'Type' with a checked checkbox and a black circle icon; 'Fire Station' with a red square icon; 'Hospital' with a red cross icon; and 'Police' with a blue diamond icon. To the right of each layer, there are icons for editing (pencil) and adding (+). A three-dot menu is visible next to the 'Emergency' layer.</p> </div> <p><i>A dynamic layer offers a high level of interactivity with the layers it is comprised of.</i></p>
<p>JMap dynamic layer (entire project)</p>	<p>Dynamic layers for the entire project are a special type of dynamic layer that presents the layers of the project with their organization (hierarchy of groups and layers). They are a quick way to deploy an application that accurately represents a JMap project. However, since they are always dynamic and can be comprised of many layers, their performance isn't optimal when there are many users.</p>

	 <p><i>A dynamic layer for the entire project shows the layer structure as it is defined in the project. It offers a high level of interactivity with all of the layers.</i></p>
<p>JMap static layer</p>	<p>Static layers are always tiled and often cached. They are a good option for data that does not change often. They can be base layers or non-base layers. They are less interactive than dynamic layers. Users can see a static layer's composition (unless it is a base layer) but they will not be able to control the visibility of each one, nor can they request the display of thematics or edit data. However, it is possible to display mouseover bubbles and make selections on the layers that make up a static layer.</p> <p>JMap static layers can be used as base layers.</p>

	 <p style="text-align: center;"><i>A static layer offers no interactivity with the layers it is comprised of.</i></p>
<p>Google Maps</p>	<p>Create a base layer that displays the Google Map. In order for this layer to display correctly with the other layers, the projection of the JMap project must be identical to the projection used by Google Maps, i.e. <b>WGS84 / Pseudo-Mercator (EPSG:3857)</b>.</p> <p>You can choose the types of maps (Roadmap, Terrain, Satellite, Hybrid, etc.) that you wish to add.</p> <div style="background-color: #e1f5fe; padding: 10px;"> <p><b>Important:</b> In order for this layer to appear, you must enter a Google Maps API key in your configuration. In the layer configuration interface, the existing key is displayed, but you cannot edit it in the interface. Refer to the <a href="#">JMap Server Settings</a> section for information on how to enter or edit a Google Maps API key.</p> <p>You must make sure you use this option in accordance with Google's license agreement.</p> </div>
<p>Bing Maps</p>	<p>Create a base layer that will display the Bing Map. In order for this layer to display correctly with the other layers, the projection of the JMap project must be identical to the projection used by Bing Maps, i.e. <b>WGS84 / Pseudo-Mercator (EPSG:3857)</b>.</p> <p>You can choose the types of maps (Road, Aerial, Aerial With Labels, etc.) that you wish to add.</p> <div style="background-color: #e1f5fe; padding: 10px;"> <p><b>Important:</b> In order for this layer to appear, you must enter a Bing Maps API key in your configuration. In the layer configuration interface, the existing key is displayed, but you cannot edit it in the interface. Refer to the <a href="#">JMap Server Settings</a> section for information on how to enter or edit a Bing Maps API key.</p> </div>

	<p>You must make sure you use this option in accordance with Microsoft's license agreement.</p>
OpenStreetMap	<p>Create a base layer that will display the OpenStreetMap map. In order for this layer to display correctly with the other layers, the projection of the JMap project must be identical to the projection used by OpenStreetMap, i.e. <b>WGS84 / Pseudo-Mercator (EPSG:3857)</b>.</p> <p>Important: You must make sure you use this option in accordance with OpenStreetMap's license agreement.</p>
GeoWebCache	<p>Create a static JMap layer by reusing an existing tile cache that is available in GeoWebCache. For more information, refer to the <a href="#">Using a GeoWebCache Server</a> section.</p>
WMTS layer	<p>Add a layer from a server that is compatible with WMTS (version 1.0.0). You must give the layer a name, indicate if you want the layer to be visible when the application opens, and also indicate if you want it to be listed in the Layers menu.</p> <p>You can use one of the project's existing layers or directly connect to an external source to obtain the data. If using the latter option, you must provide the GetCapabilities URL that will return the capabilities of the WMTS server. The URL should be similar to the following:</p> <p>http://www.server.com/wmts? SERVICE=WMTS&amp;VERSION=1.0.0&amp;REQUEST=GetCapabilities</p> <p>For example: <a href="https://basemap.nationalmap.gov/arcgis/rest/services/USGSHydroCached/MapServer/WMTS/1.0.0/WMTSCapabilities.xml">https://basemap.nationalmap.gov/arcgis/rest/services/USGSHydroCached/MapServer/WMTS/1.0.0/WMTSCapabilities.xml</a></p> <p>Afterwards, you must select the layer to add to the JMap Web application. Only layers who have the same projection as the project are selectable.</p>

The following settings apply when creating a JMap layer (static or dynamic) for JMap Web.

Properties	
Layer name	Name that identifies the layer. This name will be presented to the user in the application's layer manager. The name must be unique.

Image format	Select the format used to produce the layer images. For layers with air or satellite photos, the jpeg format usually offers the best compression rates. However, this format does not allow you to adjust the transparency of the layer, which is opaque.
Base layer	Determines whether or not the layer will be a base layer.
Visible	Determines if the layer will be initially visible or invisible when the application opens. This option does not apply to base layers.
Listed	Determines if the layer will be displayed in the layer list presented to the users. A layer may be displayed on the map without being displayed in the list of layers.
Tiled	Determines whether or not the layer images will be tiled. Static layers are automatically tiled.
Cached	Select this option if you want GeoWebCache to be used to cache the tiles generated for this layer. This option is available only for static layers. Refer to the <a href="#">Using a GeoWebCache Server</a> section for more information.
<b>Layer composition</b>	
Available layers	List of project layers available to include in the new layer.
Selected layers	List of layers selected to be included in the new layer. You can define the display order of the project layers that make up the new layer. All selected layers will be drawn together in the images produced by JMap Server.
<b>Map thumbnail</b>	
Choose	When the layer is a Base Map, you can select an image to represent it as a thumbnail in the application. The image to be uploaded must have a size of 100x100 pixels, otherwise it will be modified to reach this size. If you do not select an image, the thumbnail will display a default image.

## Geographic properties

The geographic properties of JMap Web allow you to redefine certain project properties for this application. This type of application can generate a significant workload on JMap Server and a large storage space if you use a GeoWebCache server. By reducing the global extent of the map and maximum scale, you can help reduce the load and improve performance. By default, JMap Web will use the same properties as those defined in the project.

The following parameters apply to JMap Web applications.

## Application deployment wizard

Geographic properties

1

2

Zoom to...  
- Project -

3

Maximum scale  
1 : 1 000

Allow additional levels

4

LEVEL	SCALE
1	1:559082263
...	...
20	1:1066

5

Maximum extent

X (meters)	Y (meters)	Width (meters)	Height (meters)
-19000000.0000	0.0000	15000000.0000	12000000.0000

Cancel Previous Next

Interface for configuring the application's geographic properties

- 1 Use these tools to redefine the initial and maximum extents, as needed. By default, the project's extent values are used. Limiting the maximum extent of the map can greatly reduce the size of the cached data for this type of application. The maximum extent is represented by the solid line. The initial extent is represented by the dotted line.
- 2 **Zoom to...**  
The **Zoom to...** function allows you to find data on the map. In some cases, the extents known by JMap can be incorrect, and the map displayed by default can seem empty. In order to help you locate the data correctly, this tool allows you to zoom in on the extent of a specific layer or on the extent of the entire project. Once the data has been located, you can reset valid initial and maximum extents.
- 3 **Maximum scale**  
This setting allows you to redefine the maximum scale of the map to limit the user's ability to enlarge the map. By default, the maximum scale defined in the project configuration is used but another scale can be specified. Specifying a smaller maximum scale allows you to considerably reduce the size of cached data for this type of application.

#### 4 Level/Scale

Displays the list of zoom levels and scales that will be used by the application. The levels are determined by the maximum scale and maximum extent.

##### **Allow additional levels**

This option allows JMap Web, in certain situations, to display the map at larger scales (closer zoom) than those normally used. The largest scale normally used is approximately 1:1000. If the maximum scale defined previously is larger than 1:1000 (e.g. 1:500), you must select this option to allow JMap to zoom closer.

Most base maps (Google Maps, Bing Maps, OpenStreetMap) cannot display well at scales larger than 1:1000.

#### 5 Maximum extent

The maximum extent settings are displayed below the map (X, Y coordinates of lower left point, width, height, in the coordinate system of the project). You can also enter the values directly in the respective fields.

## JMap Mobile Applications

---

### **JMap Mobile applications are replaced by JMap Survey.**

The steps to deploy JMap Web and JMap Mobile applications are very similar. See the [JMap Web Applications](#) section for more information on the general process for JMap Mobile deployment. The options that are specific to JMap Mobile are described in this section.

JMap Mobile has been specifically designed to collect data in the field. Using a device's GPS and camera as well as the forms defined in JMap Admin, users can easily conduct inventories or inspections. Another feature of JMap Mobile is that it allows users to work without a network connection.

### Editable data on JMap Mobile

Layers of points are the only type of data that can be edited (created, modified, deleted) by JMap Mobile. As configured in the JMap project, these layers must be editable and have several forms to enter attributes. In addition, JMap Mobile users must have the required editing permissions on these layers.

When JMap Mobile is deployed by the JMap administrator, the administrator must clearly indicate which layers will be editable by JMap Mobile. Thus, for each editable layer, the administrator



creates a special type of layer called a **JMap Overlay vector**. These special layers allow you to load all of the layer's data in JMap Mobile, in the form of vectors with a table of attributes. This allows you to modify the data locally.

When a network connection becomes available, the changes made to the data in JMap Mobile are immediately sent to JMap Server.

## Offline mode

Offline mode allows users to work with JMap Mobile when no network connection is available. In offline mode, the user can continue to view the map and work with editable data. All transactions conducted in offline mode are recorded on the device and sent to JMap Server when a connection (cellular or Wi-Fi) becomes available.

Working in offline mode requires some preparation on behalf of the JMap administrator. In order for the map to be available in offline mode, the layers must be tiled and cached. The levels that are to be available in offline mode must also be selected. Once these settings have been configured, the cache for the offline mode must be generated.

Refer to the section [Using a GeoWebCache Server](#) for more information on producing a tile cache and a cache for offline mode.

The following settings are specific to JMap Mobile.

Application options	
Track devices	Activate this option in order for JMap Mobile applications to continuously send their geographic position to JMap Server. This option allows you to track the movement of mobile devices in real time when the JMap Mobile application is running. Note that this requires installing JMap's Tracking extension on the server.

## Configuring layers

Configuring layers for JMap Mobile is done almost the same way as for JMap Web. See the [JMap Web Applications](#) section for more information on configuring layers. JMap Overlay vectors are specific to JMap Mobile.

Layers	
JMap Overlay vector	Create a dynamic layer that will be loaded on mobile applications in the form of vector data. Only points layers that exist in the selected JMap project can be used for this type of layer. If the user of the mobile application has the required permissions, that person can edit the data of this layer in the JMap Mobile application.

When configuring layers, the offline option allows you to select the layers that will be available in offline mode. Only static, tiled, and cached layers can be selected.

## Choosing levels for offline mode

In order to limit the size of the cache for offline mode, you must select the levels that will be available offline. This is configured in the Geographic properties window of the JMap Mobile deployment wizard.

Application deployment wizard

LEVEL	SCALE	OFFLINE
1	1:559082263	<input type="checkbox"/>
2	1:279541131	<input type="checkbox"/>
3	1:139770565	<input type="checkbox"/>
4	1:69885282	<input type="checkbox"/>
5	1:34942641	<input type="checkbox"/>
6	1:17471320	<input type="checkbox"/>
7	1:8735660	<input checked="" type="checkbox"/>
	1:4367830	<input type="checkbox"/>

Buttons: Cancel, Previous, Next

It is recommended to avoid selecting the highest levels (large scale, containing a lot of detail on a small portion of territory) because they are often too large. All the tiles of the layers for which the offline option is selected will be included in the offline cache for these levels.

Refer to the [Using a GeoWebCache Server](#) section for more information.

## WFS and WMS Services

### WMS Service

Web Map Service (WMS) is a standard set forth by the [Open Geospatial Consortium](#) that defines how client applications can obtain map images from a server that is compatible with the standard.

JMap Server can act as a WMS server. If you implement a WMS web service, other applications can query JMap Server via the WMS protocol for the selected project.

Application options	
Project	Select the JMap project that will be accessible via the WMS service.
Controlled access	Select this option if the WMS service must be secured through HTTP authentication. The selected project must allow anonymous access if this option is not selected.

Once the service has been deployed, you can click on **Launch** to display a web page containing 2 hyperlinks: the first one is the **getCapabilities** request you must provide to the applications that wish to query JMap's WMS service. The second one is an example of a **getMap** request that allows you to obtain a map image.

## WFS Service

Web Feature Service (WFS) is a standard presented by the [Open Geospatial Consortium](#) that defines how client applications can obtain vector data and its attributes (GML format) from a server that is compatible with WFS.

JMap Server can act as a WFS server. If you implement a WFS web service, other applications can query JMap Server via the WFS protocol for the selected project.

Application options	
Project	Select the JMap project that will be accessible via the WFS service.
Controlled access	Select this option if the WFS service must be secured through HTTP authentication. The selected project must allow anonymous access if this option is not selected.

Once the service has been deployed, you can click on **Launch** to display a web page containing a hyperlink towards the **getCapabilities** request you must provide to the applications that wish to query JMap's WFS service.

## Managing Deployed Applications

Once you have deployed applications, you can perform certain management tasks on them from the **Deployed Applications** interface of the **Deployed** section.

### Editing an existing application

Editing an existing application allows you to go through all configuration sections again and change any options as needed. Double-click on the application's name and select **Edit**.

## Clone an existing application

Select an application to duplicate it.

## Updating applications

Updating a deployed application means deploying it again, overwriting the existing version. This is equivalent to editing an existing application and keeping all the same options. Updating applications is useful when you install a new version of JMap to make sure your deployed application uses all the latest library versions. You do not need to update deployed applications when the data or the project changes.

## Loading and unloading applications

If you want to temporarily make a deployed application unavailable, you simply need to unload it by selecting it in the list and pressing **Unload**. When an application is unloaded, users can no longer start it using its URL. If you want to make it available again, simply press **Load** to reload it.

## Downloading applications

If an application's type is **External**, you can download that application's .war file in order to deploy it on another web server. Select the application and click on **Download**.

For more information on external applications, see [this section](#).

## Deleting applications

Deleting an existing deployed application deletes all files related to this application. There is no way to undelete an application (you need to redeploy it). Note that when deleting an application, none of your data or configurations (projects, layers, data sources, databases, etc.) are deleted nor affected in any way.

Click on this button  to access the following functions:

## Permissions

If you select a deployment, you can access the **Permissions** section of the application.

## Download REST services

The *service.war* file containing the JMap REST services is downloaded to your computer for deployment on another server.

## Download report services

The *report.war* file containing the report service is downloaded to your computer for deployment on another server.


## Using a GeoWebCache Server

---

JMap Web and JMap Mobile applications use an approach based on the production of map images generated by JMap Server. The images can be produced as a series of tiles that are adjacent to one another, for each scale level. Lower scale levels contain a small number of tiles (small scale, few details on a large portion of territory), while higher scale levels typically contain a large amount of tiles (large scale, many details on a large portion of territory).

These images are created on request when users navigate on the map in web or mobile applications. Producing these images demands a lot of work from JMap Server and therefore can cause significant delays in these applications. To improve performance, it is recommended to use a tile cache system. This system caches each tile once it is produced and can also ask JMap Server to produce all images of each layer in advance. This operation can require several hours of work during which JMap Server will be very busy. In addition, the sum total of the cached tiles can require considerable storage space. Afterwards, this will greatly accelerate navigation in web and mobile applications, since all images will have been produced and made available.

JMap Server is compatible with the open source product GeoWebCache (<http://geowebcache.org>). However, to improve integration with JMap Admin, K2 Geospatial provides its own slightly adapted version of GeoWebCache. Visit K2 Geospatial's website (<http://k2geospatial.com>) to download the GeoWebCache installer for JMap Server. In addition to providing a tile cache for JMap applications, this version of GeoWebCache can also prepare maps for offline usage in JMap Mobile applications. This will allow users to continue working without a network connection using maps that have been loaded in local mode on their devices.



*Using GeoWebCache with JMap*

## Configuring JMap to use GeoWebCache

To use GeoWebCache in conjunction with JMap Server, JMap Admin must be configured to provide JMap with the settings to connect to GeoWebCache. These settings are entered in the section JMap Server > Settings.

The URL to GeoWebCache indicates the JMap Server address that communicates with GeoWebCache. Providing more than one URL towards GeoWebCache enables web and mobile applications to launch more image queries simultaneously, which improves performance when

loading the map. These URLs must use domain names or IP addresses that point to the same GeoWebCache instance (e.g. cache1.jmaponline.net, cache2.jmaponline.net).

The username and password configured allow JMap Server to connect to GeoWebCache and send it commands. For instance, JMap Server can ask GeoWebCache to create, delete or update tile caches. These settings must match the configuration in GeoWebCache. Read below for more information on configuring GeoWebCache.

See the [JMap Server Settings](#) section for more information on configuring these settings.

## Configuring GeoWebCache

GeoWebCache is not included with JMap and must be installed separately. For more information on installing and configuring GeoWebCache, read the following [article](#).


## Using GeoWebCache for mobile and web applications

If GeoWebCache is correctly installed and configured, you can use it with web and mobile applications. Usage of GeoWebCache for these types of applications is configured when these are deployed. It is when you configure layers that you can select the Cached and Offline (mobile only) options. See [JMap Web Applications](#) and [JMap Mobile Applications](#).

In the information section of a web or mobile application that has already been deployed, there is a subsection titled **Cached layers**. This subsection displays the list of layers for which the **Cached** (JMap Web and Mobile) or **Offline** (JMap Mobile only) options were activated. This section allows you to manage caching and access the GeoWebCache management console.

### Cache state

For each layer, click on **Seed** to launch the production of the tile cache. This process can be cancelled by clicking on **Cancel**. To delete the cache for a layer, click on **Delete**. Cache production can take a very long time. If you wish to manage the cache directly in the Geowebcache interfaces, click on **Manage in Geowebcache**.



*Interface for managing cache for JMap Web and JMap Mobile applications*

### Offline cache state

You must click on **Create** in order to instruct GeoWebCache to prepare the cache for offline mode for each layer. This option is only available if the cache state for a layer is set to **Available**. This operation may take several minutes, depending on the size of the cache. If the offline cache is ready, you can delete it by clicking on **Delete**.



## Security

Security management in JMap encompasses several aspects.

Identity management can be handled by JMap Server or assigned to another system, such as Microsoft Active Directory or an LDAP directory. See the [Managing Users](#) and [Managing User Accounts and Groups](#) sections for more information. JMap also supports single sign-on for JMap Pro. See the [Single Sign-On](#) section for more information.

Access management, or rather permission management, is applied to all the resources handled by JMap. This includes user access to JMap applications as well as the access permissions of JMap administrators. See the [Managing Permissions](#) section for more information.

JMap allows you to easily use the HTTPS protocol for JMap Admin and for the various applications. See section [Using HTTPS with JMap](#) for more information.

## Managing Users

In JMap Admin, the user manager configuration can be accessed by clicking on **Users / Groups** in the JMap Server section. Select the **User manager** tab.

The user manager allows you to define how JMap will manage user accounts and groups. There are two ways to manage this information with JMap:

- Using the JMap user account database: you create and delete the user accounts directly from JMap Admin;
- By connecting to an existing database of user accounts such as a Windows Active Directory system, an LDAP compatible system or a relational database.

Several systems can also be combined to be used simultaneously (e.g. the JMap database and Windows Active Directory). These systems are then used as a single system. When JMap Server connects to an existing database, user account management is simplified because no account or user group needs to be created and managed in JMap.

The following sections describe each available option.

### JMap DB user manager

This type of user account management records users and groups directly into JMap Server's System database or in an external database containing the required tables and fields. The JMap administrator must create and manage all user accounts and groups.

Click on the **User manager** tab from the **Users / Groups** section. Select **JMap DB user manager** to indicate that user accounts will be managed within a relational database. To store information in JMap Server's System database, select the **JMap Server database** option.

You can also use any relational database that contains at least the required tables and fields by selecting the **External database** option. When you do this, an interface displays, allowing you to

define the configuration parameters. Using this configuration interface, select the database you wish to use. Afterwards, select the tables and fields containing the various information pertaining to users and groups. If needed, you can select **Read-only** mode to prevent account information from being modified by JMap Admin.

Once this configuration has been defined, you can create, modify and delete user accounts directly from JMap Admin.

### Active Directory user manager

You can connect to Windows Active Directory (in read-only mode) by selecting the option **Active Directory user manager** under **User manager**. When you select this option, a new interface is displayed, allowing you to specify the configuration parameters.

Active Directory	
Server address	Address of the Windows domain controller server configured with Active Directory.
DN	Unique identifier (Distinguished Name) pointing at the root of the directory. Composed of a list of DC (Domain Component) entries. Example: dc=ABC,dc=COM
Domain	Name of the Windows domain (e.g. ABC.COM).
User / SPN	User name that JMap Server will use to connect to the Active Directory. It is recommended to create a user especially for JMap. Its password should never expire.  If you wish to use single sign-on, you will have to create an SPN (Service Principal Name) associated with this user. See <a href="#">Single Sign-On</a> for more details.
Password	Password of the user JMap Server will use to connect to the Active Directory.
Admin. password	A user named <b>administrator</b> must always exist in JMap. If no <b>administrator</b> user exists in the Active Directory, JMap will simulate one. In such a case, provide the password associated with this user. If the user <b>administrator</b> does exist in the Active Directory and a password is entered, this password will simply be ignored.
Enable single sign-on	Enables the single sign-on option. See <a href="#">Single Sign-On</a> for more details.
Default / Custom LDAP configuration	Active Directory is based on LDAP. This option allows for the use of LDAP parameters that are most commonly used for Active Directory. However, if those parameters don't match the ones in use, it is possible to specify custom values.

Max page size	Active Directory limits the transaction size to a maximum number of records at a time (page size). The value of this parameter must not be greater than the maximum size authorized by Active Directory (1000 is the default value in Active Directory). If the size is too small, this can reduce performance. A size greater than the authorized limit will cause missing data in the user list.
---------------	--

### JMap LDAP user manager

You can connect to any LDAP compliant directory (in read-only mode). Unix, Linux and Windows systems offer many LDAP compliant directories.

To use this option, select **JMap LDAP user manager** under **User manager**. When you do so, a new interface is displayed, allowing you to specify the configuration parameters.

JMap LDAP user manager	
Server URL	LDAP server address.
DN	Unique identifier (Distinguished Name) used to define the root of the directory. Includes a list of Domain Component entries. For example: dc=ABC,dc=COM
User	User name that will be used by JMap Server to connect to the LDAP directory. It is recommended to have a user created specifically for JMap purposes. This user's password should never expire.
Password	The user password that JMap Server will use to connect to the LDAP directory.
Admin. password	A user named <b>administrator</b> must always exist in JMap. If there is no <b>administrator</b> user in the LDAP directory, JMap will simulate one. In this case, you must provide the password associated with this user. If the <b>administrator</b> user exists in the LDAP directory and a password is entered, it will be ignored.
Authentication prefix	Some LDAP servers require a prefix to be concatenated with the user name in order to proceed with authentication.  Example: Prefix: a_domain\ User: a_user Result: a_domain\a_user

<b>JMap LDAP user manager</b>	
Authentication suffix	Some LDAP servers require a suffix to be concatenated with the user name to proceed with authentication.  Example: Suffix=@a_domain User=a_user Result: a_user@a_domain
User class	Name of the LDAP object class used to identify a user in the LDAP directory.
Group class	Name of the LDAP object class used to identify a group in the LDAP directory.
User filter	Search filter used to extract users from the LDAP directory. This filter must be formatted according to the standard LDAP syntax.
Group filter	Search filter used to extract groups from the LDAP directory. This filter must be formatted according to the standard LDAP syntax.
User attribute	The attribute of an LDAP user that defines this user's identity.
Group attribute	The attribute of an LDAP group that defines this group's identity.
Member attribute	The attribute of an LDAP group that defines which users are members of this group.
Full name attribute	The attribute of an LDAP user that defines this user's full name.
Email attribute	The attribute of an LDAP user that defines this user's email address.
Max page size	In LDAP directories, the size of transactions is limited to a maximum number of recordings at once (the size of the page). The value of this parameter must not exceed the maximum size permitted by the directory (1000 is the default value in LDAP directories). If the size is too small, this could affect performance. If the size is larger than the authorized limit, data will be missing in the user list.

For more information on the LDAP protocol, refer to [http://en.wikipedia.org/wiki/Lightweight\\_Directory\\_Access\\_Protocol](http://en.wikipedia.org/wiki/Lightweight_Directory_Access_Protocol).

## Composite user manager

This type of user management allows you to combine several managers together. You can add as many user managers as necessary. All user managers will function as a single user manager. Refer to the previous sections for information on user manager configuration.

## Synchronizing user permissions

When you connect to an existing user account database (Active Directory, LDAP or external relational database), it may be useful to synchronize JMap Server with the database for 2 reasons:

- When users or groups are deleted from the database and those deleted users or groups had been given permissions in JMap (e.g. to open a project or view certain layers), the permissions are not deleted from JMap Server permission lists. This can happen because JMap Server is not aware the users or groups have been deleted from the database. When synchronizing, JMap Server removes all existing permissions for deleted users and groups. However, even if you don't synchronize, there is no security problem because deleted users will fail at login.
- When the contents of user groups are modified (members added or removed), so that JMap Server can reload the lists of users that belong to the groups. JMap Server keeps the group member lists in memory for performance reasons.

You can automate the synchronization by selecting the option **Synchronize automatically every...** and specifying a time period.

## Managing User Accounts and Groups

In JMap, user accounts and groups are used for access control and collaboration purposes. You can manage users and groups in JMap Admin by clicking on **Users / Groups** from the JMap Server section.

Two special users and two special groups always exist in JMap: **administrator**, **anonymous**, **everyone**, and **authenticated users**.

Special users and groups	
Administrator	The <b>administrator</b> user allows you to access JMap Admin following a new installation (this user has administration rights in JMap). This user's password field is left blank, therefore, it is highly recommended to add a password as soon as possible. Read below for more information. The <b>administrator</b> user always exists in JMap and cannot be deleted.
Anonymous	The <b>anonymous</b> user allows users who are not authenticated to access certain resources. It can be used to configure access to a project without

	authentication, for instance. The anonymous user always exists in JMap and cannot be deleted. In addition, this user's password (blank) cannot be modified.
Everyone	The <b>everyone</b> group is used to give all users access to a resource, provided they are authenticated. The everyone user is not displayed in the list of JMap groups. It is only visible in interfaces that allow you to define permissions, where applicable.
Authenticated users	The <b>authenticated users</b> group is used to allow all users except <b>anonymous</b> to access a resource. Authentication is required for this group.

## Creating users and groups



You can create a new user or group by pressing **Create** from the **Users / Groups** section. This will bring you to the new user or group configuration section. Note that you can only create users and groups if you are using the JMap account database or an external database that is not in read-only mode.

Users	
User name	Enter a unique user name (login name) for the new user. You will not be able to save it if the name already exists.
Password	Enter a password for the new user. The password field can be empty but this is not recommended. Users of JMap Web applications can change their password from the application. This is only possible if the user accounts are managed with JMap DB user manager.
Confirm password	Enter the password a second time to confirm.
Full name	Enter the full name (first name and last name) for the new user. This is optional.
Email	Enter the email address of the new user. It is used when sending maps to the user. This is optional.
Hidden	Select this option if you want the new user to be hidden from user directories.

## Groups

Group name	Enter a unique group name for the new group. You will not be able to save it if the name already exists.
------------	--

## Modifying users and groups

You can modify an existing user or group by clicking on its name in the list. Note that once a user is created, its user name cannot be modified. To add users to a group, press  and a list of available users will be displayed. Select the users to add to the group and press **Add**. To remove users from a group, select the users to remove and press .

## Deleting users and groups

You can delete a user or group by selecting it in the list and pressing **Delete**.

## Managing Permissions

Permissions in JMap are divided into 2 families: permissions for the users of applications (Pro, Web and Mobile) and permissions for the administrators (JMap Admin).

### User permissions

User permissions determine what the users can do inside JMap Pro, JMap Web, and JMap Mobile applications.

The following table presents the different permission groups that are available for the users.

User permissions	
Permissions on projects	See section <a href="#">Project Permissions</a> for more information.
Permissions on layers	See section <a href="#">Layer Permissions</a> for more information.
Permissions on personal layers	<p><b>Create personal layers</b></p> <p>This permission gives a user the right to create personal layers in JMap Pro applications. By default, JMap users are not allowed to create personal layers.</p> <p>You can configure this permission in subsection Permissions of the JMap Server section.</p>

Permissions on forms	See section <a href="#">Database Forms</a> for more information.
----------------------	--

## Administrator permissions

Administrator permissions determine what JMap administrators are authorized to do in JMap Admin. Some permissions are global (permissions to do some tasks) while other permissions apply to specific resources.

Several of the global permissions are configured in the **Permissions** subsection of the JMap Server section.

The following table describes the global administration permissions.

Global administration permissions	
Access JMap Admin	This permission is required for an administrator to access JMap Admin. After the installation of JMap, only the <b>administrator</b> user has this permission. Note that the password is initially left empty for this user. It is strongly recommended to enter a password for the <b>administrator</b> user. See section <a href="#">Managing User Accounts and Groups</a> for more information on modifying passwords.  Also make sure to leave at least one user with this permission and with a known password. Otherwise, it will be impossible to access JMap Admin.
Create database	This permission is required for an administrator to create new databases in JMap Admin.
Create remote connection	This permission is required for an administrator to create new connections to remote JMap Server instances in JMap Admin.
Create deployment	This permission is required for an administrator to create new application deployments in JMap Admin.
Create metadata templates	This permission is required for an administrator to create new metadata templates in JMap Admin.
Create style templates	This permission is required for an administrator to create new style templates in JMap Admin.
Create project	This permission is required for an administrator to create new projects in JMap Admin.
Create data source	This permission is required for an administrator to create new spatial data sources in JMap Admin.



Administration permissions that are specific to resources determine what an administrator can do with each resource. The following table describes those permissions.

Resource specific administration permissions	
Access ...	<p>The administrator can view the detailed information of a resource and use the resource, but cannot modify it.</p> <p>Example: To use a spatial data source in order to create a layer, the administrator must at least have the <b>Access</b> permission on the data source.</p>
Administrate ...	<p>Allows the administrator to modify the resource and manage the user permissions for the resource. Does not allow the administrator to delete the resource or manage its administration permissions.</p> <p>Example: To add a layer in a project, the administrator must have the <b>Administrate</b> permission for the project.</p>
Use SQL console	<p>(Applies only to databases) Allows the administrator to use the SQL console on the database. The SQL console is used to show the database structure and to execute SQL queries on the database.</p>
Remote access	<p>Allows the administrator to access the resource from another instance of JMap Server. This permission is generally granted to a generic account used to open communication sessions between different instances of JMap Server.</p> <p>For more information, see sections <a href="#">Sharing Layers</a> and <a href="#">Sharing Spatial Data Sources</a>.</p>

## Owners of a resource

Most resources managed in JMap Admin have one or more owners. Owners of a resource are the only ones that are allowed to:

- manage administration permissions for the resource;
- manage the list of owners for the resource;
- delete the resource.

## Super administrators

Super administrators are special accounts that can do everything in JMap Admin. They are the only ones who are allowed to:

- manage the list of super administrators;

- manage global administration permissions;
- manage users and groups;
- modify JMap Server's working parameters;
- display the log files;
- import and export configurations.

You can manage the list of super administrators from subsection **Permissions** in section JMap Server. Select the **Super administrators** tab.

The following table presents administration tasks with examples, and indicates which profile or permission is required to perform each task.


Tasks	Super Administrator	Administrator
<b>Access JMap Admin</b>	YES	If permission Access JMap Admin
<b>Manage the list of Super administrators</b>	YES	NO
<b>Manage global administration permissions</b>	YES	NO
<ul style="list-style-type: none"> <li>• Give an administrator permission to create projects</li> <li>• Remove an administrator's permission to create spatial data sources</li> <li>• Give an administrator permission to create metadata templates for layers.</li> </ul>		
<b>Perform management tasks for JMap Server</b>	YES	NO
<ul style="list-style-type: none"> <li>• Modify JMap Server's working parameters (ports, memory, etc.)</li> <li>• Manage users and groups</li> <li>• Import and export JMap Server configurations</li> <li>• View log files or modify their settings</li> </ul>		Can change user account password
<b>Create a resource</b>	YES	If permission Create ...
<ul style="list-style-type: none"> <li>• Create a project</li> <li>• Create a database</li> <li>• Create an application deployment</li> </ul>		

<p><b>Use a resource</b></p> <ul style="list-style-type: none"> <li>• Use a database to create a spatial data source</li> <li>• Use a data source to create a layer</li> <li>• Use a connection to JMap Server to create a layer by reference</li> </ul>	YES	If permission Access ...
<p><b>View detailed information about a resource</b></p> <ul style="list-style-type: none"> <li>• Click on a database and view all of its parameters</li> <li>• Click on a project to view all of its parameters</li> </ul>	YES	If permission Access ...
<p><b>Modify a resource</b></p> <ul style="list-style-type: none"> <li>• Change the name of a project</li> <li>• Add a layer in a project</li> <li>• Modify the connection parameters for a database</li> <li>• Modify the projection of a spatial data source</li> </ul>	YES	If permission Administrate ...
<p><b>Delete a resource</b></p> <ul style="list-style-type: none"> <li>• Delete a project</li> <li>• Delete an application deployment</li> <li>• Delete a style template</li> </ul>	YES	If owner of the resource
<p><b>Manage user permissions of a resource</b></p> <ul style="list-style-type: none"> <li>• Give a user permission to open a project</li> <li>• Give a user permission to edit the elements of a project layer</li> <li>• Remove a user's permission to copy the data of a project layer</li> </ul>	YES	If permission Administrate
<p><b>Manage the administrator permissions of a resource</b></p> <ul style="list-style-type: none"> <li>• Give an administrator permission to use a spatial data source</li> </ul>	YES	If owner of the resource

- Give an administrator permission to modify a project
- Remove an administrator's permission to modify a database

**Manage the list of owners of a resource**      YES      If owner of the resource

## Permission reports

Permission reports allow you to view all the permissions that a user or a group has on a single report. A permission report is a convenient way to get the information without checking every resource. The reports are accessible from the **Users** and **Groups** tabs in the **Users / Groups** section, by clicking on  .

## Single Sign-On

Single sign-on provides a secure way for users to access JMap Pro applications without authentication. The Windows session authentication is used to automatically launch the JMap session. Single sign-on is only available for Windows environments using Active Directory. A special configuration is required on the Windows server and on each computer where single sign-on is wanted. Note that the **Enable single sign-on** option must also be selected when deploying a JMap Pro application.

For more details on single sign-on configuration, refer to [this article](#).

## Managing Sessions

Each user that is connected to JMap Server using a JMap application has an open session on the server. The session remains open as long as the JMap application is not closed. Sessions contain information about the identity of the user. Depending on your license agreement, you may be limited to a certain number of simultaneous sessions.

To access the session management section, click on **Sessions** in the **JMap Server** section.

Five different types of sessions are possible. The following table describes each type of session.

Type of JMap session
----------------------



JMap Pro	This type of session is used when a user connects to JMap Server using a JMap Pro application. The number of concurrent sessions of this type is defined by your JMap license.
JMap Mobile	This type of session is used when a user connects to JMap Server using a JMap Mobile application. The number of concurrent sessions of this type is defined by your JMap license.
JMap Web	This type of session is used when a user connects to JMap Server using a JMap Web application. The number of concurrent sessions of this type is defined by your JMap license.
JMap Admin	This type of session is opened when a user connects to JMap Admin to administrate JMap Server. This type of session is not controlled, therefore the number of concurrent JMap Admin sessions is unlimited.
JMap Server	This type of session is used when a JMap Server connects to another JMap Server. The session opens on the server that accepted the connection. This type of session is used for JMap to JMap data sharing. This type of session must be authorized by your JMap user license.

## Active sessions

You can view the list of open sessions. By selecting the **Active sessions** tab, the list of current sessions will be displayed along with useful information on each session. You can close open sessions by selecting them and clicking on **Close session(s)**.

## Reserved sessions

Reserved sessions are special sessions for users who have priority over the other users. These users can always open a JMap Pro, JMap Web or JMap Mobile session, even if the maximum number of sessions is reached, according to your license. These reserved sessions are recorded separately from the rest of the sessions.

If your JMap user license permits it, you can assign a certain number of reserved sessions to the users of your choice. Press  to select a user and assign him/her a reserved session. Once the maximum number of reserved sessions has been assigned, you cannot assign any to other users. You can remove a reserved session from a user by selecting that person's name and clicking on .

## Statistics

Session statistics provide basic information on user activity over time. You can determine the total number of sessions over a given period and the highest number of concurrent sessions reached

over a period of time. Statistics are displayed in a bar graph. Click on **Update** to generate the graph.

Session statistics	
Display	Select the information to display, either the <b>Total number of sessions</b> or the <b>Highest number of concurrent sessions</b> .
Users	Select one or more users for which the information will be displayed.
Time unit	Select the time unit to be used to display information. Possible units are <b>Hour, Day, Week</b> or <b>Month</b> .

The sessions information is stored in the JMap System database for a period of 18 months. Sessions that are older than 18 months are automatically deleted from the System database.

## Using HTTPS with JMap

The HTTPS protocol allows you to use JMap in a more secure way by encrypting all communication between JMap, JMap Admin, and JMap Server applications.

### Using HTTPS with JMap Admin

In order to use HTTPS with JMap Admin, you must install a security certificate in JMap Server. A security certificate is required for data encryption.

During the JMap installation process, an option is available to create and automatically install a temporary security certificate. This type of certificate ensures communication will be well secured, but it will cause warning messages to display in web browsers because it is not issued by a recognized security organization (CA or Certificate Authority).

You can also install a security certificate issued specifically for your organization, if you have one. For detailed steps on how to install a certificate, read the following article:  
<https://k2geospatial.atlassian.net/wiki/x/EQAtAQ>.

Once the security certificate has been installed in JMap Server, you can launch JMap Admin with a URL similar to the following:

<https://myserverjmap> (assuming the default port 443 is used)

At any time, if you wish to force the use of the HTTPS protocol for JMap Admin, you can enable automatic redirection. For more information, refer to the [JMap Server Settings](#) section.

## Using HTTPS with JMap applications

When you deploy JMap applications (Pro, Web or Mobile) with JMap Admin, you can indicate which protocol (HTTP or HTTPS) will be used for communication between the application and JMap Server. If the deployment type is **local** (app hosted on JMap Server), the HTTPS protocol is available only if a security certificate is installed on the JMap Server. It is the same certificate as that which is used for JMap Admin (read above). If the deployment type is **external** (app hosted on another Web server), the 2 protocols are always offered.

For JMap Pro, the HTTP and HTTPS protocols are used only if the Proxy connection option is selected during deployment.

## JMap Server Management

The following sections cover JMap Server management tasks.

### JMap Server Status

The **Status** section of JMap Admin provides a lot of useful information for monitoring JMap Server. Additionally, this section provides detailed information on your license agreement. Each part is explained below.

General	
Version	Complete information on the JMap Server version. Provide this information when requesting technical support.
IP Address	IP address of the host running JMap Server.
Port	TCP/IP port used by JMap Server for connections with JMap Pro and other JMap Server instances.

Sessions	
Total active sessions	Number of currently active user sessions.
Active JMap Pro sessions	Number of current user sessions for JMap Pro applications. The maximum number of sessions authorized by the license for this type of application is indicated.
Active JMap Web sessions	Number of current user sessions for JMap Web applications. The maximum number of sessions authorized by the license for this type of application is indicated.
Active JMap Mobile sessions	Number of current user sessions for JMap Mobile applications. The maximum number of sessions authorized by the license for this type of application is indicated.
Active JMap Server sessions	Number of current JMap Server sessions. The maximum number permitted for this type of session is indicated.
Administrators	User names of administrators currently connected to JMap Admin. The computer host name or IP address from which the administrators are connected are also indicated.



<b>Resources</b>	
Java VM	Version of the Java virtual machine used by JMap Server.
Process Id	The ID number of JMap Server's system process.
Available processors	Number of processors used by the JMap Server process.
Memory usage	Portion of the allocated memory actually used by JMap Server.
Memory allocated	Total amount of memory allocated for JMap Server by the operating system. If the memory usage reaches this limit, more memory (if available) will be allocated by the operating system. The maximum memory that can be used by JMap Server is defined in the startup parameters during installation.
Thread pool usage	Number of simultaneous request processors (threads) currently in use (compared to number of initialized threads).
Thread pool usage peak	Maximum usage value reached since server startup (helps determine optimal size of initial pool).
Started since	Date and time JMap Server was last started.

<b>Cache</b>	
Memory cache usage	Proportion of the memory data cache used by JMap Server compared to the defined limit and relative percentage.
Memory cache efficiency	Number of times requested data is found in the memory cache, expressed as a percentage of the total number of data requests.
Disk cache usage	Proportion of the disk data cache used by JMap Server compared to the defined limit and relative percentage.
Disk cache efficiency	Percentage of times requested data is found in the disk cache compared to the total number of data requests.

<b>License information</b>	
Model	Licensing model in use. Click on the link to view the content of the license agreement.
Licensed to	Organization licensed to use JMap Server.

Serial number	Unique serial number of JMap Server.
Maximum users	Maximum number of users that can be created in JMap, according to license.
Maximum concurrent JMap Pro sessions	Maximum number of concurrent sessions that can be opened by JMap Pro applications, according to license.
Maximum concurrent JMap Web sessions	Maximum number of concurrent sessions that can be opened by JMap Web applications, according to license.
Maximum concurrent JMap Mobile sessions	Maximum number of concurrent sessions that can be opened by JMap Mobile applications, according to license.
Maximum projects	Maximum number of projects that can be created in JMap, according to license.
Multiple sessions	Authorization to have multiple concurrent sessions for the same user.
Expiration	Expiration date of the license. Beyond this date, JMap Server will refuse to start.
Licensed products	List of JMap modules that are authorized by the license.

## Exporting and Importing

### Exporting and importing the JMap configuration

Your JMap Server configuration (spatial data sources, databases, projects, layers, etc.) is stored on a disk in binary format. This configuration is only accessible by JMap Server and is only compatible with your current version (main version, e.g. 7.X). Using the export tool, a text version of this configuration can be produced. This exported configuration can then be imported back into JMap Server, with the same settings or different ones. The configuration can even be exported to a newer version. Here are a few examples where exporting and importing your configuration can be useful:

- You installed a new version of JMap with major changes and you want to reuse your existing configuration. You can export the configuration from your older JMap version and then import it in the newer version.
- You manage many instances of JMap Server and you need to move a project from one instance to another. You can do a partial export to move only the project you need and then import it in the other instance.

- You need to replicate your development environment to the production environment. You can do a full export from your development server and then import it in the production server.

To access export and import tools, select **Import / Export** in the JMap Server section.

## Exporting

When exporting a configuration, you must choose whether you want to export the complete configuration or some specific resources (partial exportation). If you choose to export specific resources, you must select if you want to export databases, spatial data sources, projects, style templates or metadata templates. There is a dependency relationship between these different resources: projects depend on spatial data sources and style templates while spatial data sources may depend on databases. Consequently, if you export a project, then spatial data sources, style templates, and possibly databases will also be exported.

The exportation process creates up to 4 files: the .properties file is the main exportation file and contains the configuration information. All files are necessary for the importation. You can determine the destination directory and file name.

## Importing

When importing a configuration, you have the choice to import a complete configuration (complete importation) or only a portion of it (partial importation). You can only do a complete importation if the exportation files contain a complete exportation. **When doing a complete importation, any existing configuration in JMap Server is deleted and replaced by the imported configuration.** When a full importation is completed, you will automatically be sent back to the JMap Admin login page.

When doing a partial importation, there may be situations where the imported resources already exist (identical names). In these cases, you have to tell JMap Admin which action to take: replace the existing resource or create a new one with a different name. The file type data sources that you import are not ready to use and must be updated after the importation.

## Exporting and importing JMap user data

JMap user data includes all data created or modified by users. This includes user preferences, contexts, personal layers, data from editable JMap layers, etc. If you change JMap Server instances and you wish to keep all existing user data, you must export it from the previous server and import it into the new server.

## Exporting

When you export user data, you must decide whether to export all data, only the editable layers stored in JMap (including personal layers) or only the workspaces (including contexts, user preferences, etc.).

## Importing

When you import user data, there may be situations where imported resources already existed (identical names). In these cases, you must indicate which action JMap Admin must take: replace the existing resource or create a new one under a different name.

## User Data

---

JMap application users can generate certain data that will be stored in the JMap Server environment.

This can include various types of data, including user preferences (choice of units, print settings, etc.), map contexts (JMap Pro and JMap Web) and customized print layouts.

Map context data is stored in JSON format in the JMAP\_CONTEXTS table of the System database.

Non-context data is stored in separate folders for each user. The parent folder of these user folders is

```
(JMap_Home)\workspaces\
```

Note that this folder can have a different location if you indicate a different folder in the `server.workspaces.path` line of the `jmapserver.properties` file and manually copy the files and subfolders.

In some cases, the administrator may have to copy certain files when a migration occurs or when these files need to be shared with other users. The following sections describe each of these situations in detail.

Note that the functions to export and import JMap configurations also handle user data.

## Contexts

Map contexts are comprised of all the parameters that allow a JMap Pro or JMap Web user to recreate a geographic map. Contexts can be used to save maps and even share them between users. Existing contexts can be recalled easily to recreate a map environment. All layer parameters, annotations, thematics, selections, etc. are part of the context and are recreated when the context is opened.

A context is associated with the project in which it was created. It cannot be accessed in other projects.

## Personal Layers

The [Personal Layers](#) section provides more information on managing personal layers and how to make them public. The data from personal layers is not stored in the workspaces folder; instead, it is saved directly in JMap Server's System database (one table per personal layer).

Export and import tools can handle the data of personal layers.

## JMap Spatial Tables

As with personal layers, the data from editable layers of JMap projects is stored directly in JMap Server's System database, in tables that are called JMap Spatial tables.

Export and import tools can handle the data from JMap Spatial tables.

## Print Layouts

The users of JMap Pro applications can create their own print layouts. The files are stored in the folder

```
(JMap_Home)\workspaces\\printLayouts
```

The print layouts created by users can be made public. To do this, you must copy the files in the following directory:

```
JMap_Home)\workspaces\public\printLayouts.
```

Public print layouts can be accessed by all JMap Pro users.

## JMap Server Settings

These parameters have an impact on the behaviour and performances of a JMap Server system.

Press Save to save all modifications. Click on  to reread parameters from configuration files if they have changed. The configuration files are located in **JMAP\_HOME/conf**.

General	
JMap Server name	You can give a name to this JMap Server instance. This name will be displayed in the authentication screen and in the JMap Admin header.
Default language	You can select the default language that will be selected automatically when creating new projects.
Available languages	You can select the available languages that will be automatically selected when creating new projects.

Ports	
Server port	TCP/IP port used by JMap Server for connections with JMap Pro and other JMap Server instances.

Web server port	TCP/IP port that JMap Server embedded web server listens to for HTTP requests. Used for JMap Admin and for local application deployments.
Web server port (https)	TCP/IP port that JMap Server embedded web server listens to for HTTPS requests.

**Network**

Preferred external service address	The proxy address used to deploy the applications. When configuring a new deployment, you can change the local address to this external address.
Preferred JMap Server address	The local address of JMap Server used to deploy the applications. When configuring a new deployment, you can change the external address to this local address.
Server port	TCP/IP port used by JMap Server for connections with JMap Pro and other instances of JMap Server.
Web server port	TCP/IP port used by the integrated JMap Server web server for HTTP requests. Used for JMap Admin and local application deployments.
Web server port (https)	TCP/IP port used by the integrated JMap Server web server for HTTPS requests.

**Caching**

Memory size	Size of memory cache. Holds previously loaded vector data tiles to minimize data source queries. This helps improve JMap Server performances. Cache statistics can be viewed in JMap Server Status section.
Disk size	Size of disk cache. Its operation is similar to the memory cache. Unlimited size is recommended.
Imaging size	Size of memory cache dedicated to imaging operations. This cache is used by JMap Server when processing image files (raster data sources that read image files). It dramatically helps improve JMap Server performances when working with high volume images.

**HTTPS**

Redirect	Automatically redirects JMap Admin users to a secure connection (https). This option is only available if there is a security certificate. For more information, refer to <a href="#">Using HTTPS with JMap</a> .
----------	---

<b>HTTP Proxy</b>	
Host	Host name or address of HTTP proxy server. Is used if JMap Server must go through an HTTP proxy to access systems outside of the local network.
Port	TCP/IP port used to connect to the HTTP proxy server.
Username	Username used to connect to the HTTP proxy server.
Password	Password used to connect to the HTTP proxy server.

<b>SMTP (Mail server)</b>	
Host	Host name or address of SMTP server. JMap Server requires an SMTP server to send emails.
Port	TCP/IP port used to connect to SMTP server.
Username	Username used to connect to the SMTP server (if needed).
Password	Password used to connect to the SMTP server (if needed).
Encryption	Select an encryption method if required by the SMTP server.

<b>GeoWebCache</b>	
URL (1-4)	Enter one or more URLs to connect to the GeoWebCache server. Only one URL is necessary, but entering several URLs that point to the same server will optimize the use of this type of server.  Configuring settings for GeoWebCache is optional but offers better performance for JMap Web and JMap Mobile applications. Refer to the <a href="#">Using a GeoWebCache Server</a> section for more information.
Username	User name used to connect to the GeoWebCache server.
Password	Password used to connect to the GeoWebCache server.

Route Logistics Service	
URL	Enter the URL of the RLS service to use (e.g. <a href="https://rls.jmaponline.net/rls/rest/v1.0">https://rls.jmaponline.net/rls/rest/v1.0</a> ). This service allows you to geocode addresses and calculate optimal routes.
Client ID	Enter your organization's unique key that allows you to use the RLS services.

API Keys	
Google	Enter the API key of your organization that allows you to use Google services. For more details, visit the following page: <a href="https://developers.google.com/maps/documentation/javascript/get-api-key?hl=Fr">https://developers.google.com/maps/documentation/javascript/get-api-key?hl=Fr</a>
Bing	Enter the API key of your organization that allows you to use Bing services. For more details, visit the following page: <a href="https://msdn.microsoft.com/fr-fr/library/ff428642.aspx">https://msdn.microsoft.com/fr-fr/library/ff428642.aspx</a>

File browser	
Allow upload	Select this option if you allow uploading files to JMap Server directly from JMap Admin.
Max. upload file size	Specify the maximum size of a file to upload. Select the Unlimited option if you do not set a limit on file size.
Upload root folder	Specify the directory where the uploaded files will be copied. Each administrator account in JMap has a subdirectory automatically created in the <i>JMAP_HOME/Data/Uploads</i> directory. Uploaded files are accessible to all JMap Admin users. The Uploads directory is also available when creating spatial data sources.

Loaded parameters	
Database drivers	List of loaded database drivers. New drivers can be added by creating new configuration files in the directory <i>JMAP_HOME/conf/db</i> on the server.



Custom spatial data sources	Spatial data sources related to certain specific applications.
Projections	List of loaded projections. New projections can be created by adding entries in the file <code>JMAP_HOME/conf/projections.properties</code> on the server.
Element factories	Map element generation modules related to certain specific applications.
User managers	List of loaded user manager modules. User managers are used to manage users and groups and they provide the authentication service used in JMap Server.

## Usage Statistics

Usage statistics offer the JMap administrator information on the usage of projects, layers, and contexts. JMap Server records some of the users' activity and allows you to generate reports, which contain statistics on the use of resources in JMap Pro and JMap Web applications. This data can be useful to assess the relevance of projects or layers that are seldom or never used.

In order for usage data to be recorded, you must select the **Usage statistics** option when creating or editing a project. For more details on this topic, refer to the [Creating Projects](#) section. When exporting or importing your project, your choice will be saved in the exported configuration.

Thus, whenever a user opens a project, views a layer, or views or creates a context in a JMap Pro or JMap Web application, this activity will be automatically recorded in a temporal table of the System database. Every night, at a set time, the data will be aggregated into two tables (`JMAP_STATISTICS_MONTHLY` and `JMAP_STATISTICS_YEARLY`), and it will then be displayed in this section of JMap Admin. The data aggregation frequency can be configured in JMap's settings. To do so, you must modify the `server.statistics.config.cron` variable in the `jmapserver.properties` file that is found in the `JMAP_HOME/conf` folder. This page <http://www.quartz-scheduler.org/documentation/quartz-2.3.0/tutorials/crontrigger.html> offers details about cron expressions. Information about the activity of users who were deleted is recorded in both tables. The details of the aggregation functions are found in JMap Admin's REST API.

Information entered in the temporal table will differ slightly between JMap Pro and JMap Web applications. Usage data originating from JMap Pro will be saved when the JMap Pro application is closed, or when the project is closed because the user has switched to another project.

## Calculating statistics

### Project statistics

From	Select the start date of the period for which the statistics will be calculated.
To	Select the end date of the period for which the statistics will be calculated.
User	Select the user whose statistics you want to obtain. If the user who opened the project was eliminated from JMap, his or her usage statistics will be added to the System user and displayed under this user.
Project name	Enter the name of the project for which you want to obtain statistics. You can enter part of the project's name, and all the projects whose names coincide in part with the name you entered will be displayed.
Open count	The result indicates the number of times that the user opened the project in a JMap Pro or JMap Web application. Note that the data originating from JMap Pro will be saved when the application is closed, or when the project is closed because the user has switched to another project.

Click on **Apply** to generate the statistics by project. Click on **Reset** to delete the statistics.

Layer statistics	
From	Select the start date of the period for which the statistics will be calculated.
To	Select the end date of the period for which the statistics will be calculated.
Project name	Select the project that contains the layer(s) whose statistics you want to calculate.
User	Select the user whose statistics you want to obtain. If the user who opened the project was eliminated from JMap, his or her usage statistics will be added to the System user and displayed under this user.
Layer name	Enter the name or part of the name of the layer(s) whose statistics you want to calculate.
View count	The result indicates the number of times the user viewed the layer(s) in a JMap Pro or JMap Web application. One view will be counted for each user session. When the layer is visible in the map, one view is counted. If the user disables the layer's visibility and enables it again during a session, only one view will be counted.

	Note that the data originating from JMap Pro will be saved when the application is closed, or when the project is closed because the user has switched to another project.
--	--

Click on **Apply** to generate the statistics by layer. Click on **Reset** to delete the statistics.

<b>Statistics on public contexts</b>	
From	Select the start date of the period for which the statistics will be calculated.
To	Select the end date of the period for which the statistics will be calculated.
Filter	<p>Three filters allow you to calculate various statistics.</p> <p><b>Created by user:</b> Calculates the number of contexts created by the user for a given project.</p> <p><b>Used by project:</b> Calculates the number of times a public context is opened by all JMap Pro users for a given project.</p> <p><b>Used by project and user:</b> Calculates the number of times a public context is opened by a JMap Pro user for a given project.</p> <p>JMap Web contexts are private. JMap only calculates the statistics for public contexts, used in JMap Pro applications.</p>
User	Select the user whose statistics you want to obtain. If the user who opened the project was eliminated from JMap, his or her usage statistics will be added to the System user and displayed under this user.
Project name	Enter the name of the project for which you wish to obtain statistics on the contexts.
Create count	Calculates the number of contexts created during the selected period for the user and project selected in JMap Web and JMap Pro applications.
Context name	Enter the name of the public context for which you wish to obtain statistics.
Use count	Indicates the number of times the public context was opened, either by all users of a project in a JMap Pro application, or by a specific user of a project in a JMap Pro application.

Select the filter you wish to use and click on **Apply** to display the settings used to define the calculation. Once the settings have been completed, click on **Apply** again to produce the statistics. Click on **Reset** to delete the statistics.

## Exporting reports

You can export the generated report in Excel or PDF format. To do so, once the statistics have been calculated, click on **Excel** or **PDF** to automatically download a file in the selected format.

## Log Files

Log files contain information on the activities that are performed in JMap Server. The quantity of events written in the log files depends on the selected logging level. By default, a new log file is created every day but this parameter can be adjusted. By default, log files are located in the directory **JMAP\_HOME/logs**. You may need to periodically check the volume of the log files and archive or delete old ones.

Configuration	
Log level	<p>The maximum level of the messages added to the log files. For example, if Warning is selected, only messages with a level of Warning, Error or Fatal will be written in the log files. The following log levels are available (listed in descending order):</p> <p><b>All:</b> Every event is written. Use only to solve a problem.</p> <p><b>Debug:</b> Debug level events are written. Use only to solve a problem. All lower level events are also written.</p> <p><b>Info:</b> Information level events are written. This includes user logins. All lower level events are also written.</p> <p><b>Warning:</b> Warning (non serious) level events are written. All lower level events are also written.</p> <p><b>Error:</b> Error (serious) level events are written. All lower level events are also written.</p> <p><b>Fatal:</b> Only fatal error (very serious) events are written.</p> <p><b>Off:</b> Nothing is written.</p>
Log file directory	<p>Directory where to create the log files. Default is under <code>JMAP_HOME/logs</code>. Make sure there is sufficient disk space to hold log files.</p>


File age limit	The file age limit determines how often new log files are created. The current log file is always called jmap_log. When a new file is created, the current log is renamed to include the date (e.g. jmap_log_2006_05_23.log).
Messages to console	Determines if events will also be written in JMap Server screen console. This is useful for tests or development but should be turned off during production. Moreover, when JMap Server has no output console (started as a background process or as a service on Windows), this option is useless and consumes server resources for nothing.

## Viewing log files

Log files (and error files) can be viewed directly in JMap Admin. Select the name of a file from the list to open it. The content of the file is displayed. Note that error files are also listed along with log files. The error files contain only error messages that can sometimes complement the log files to help solve a problem.

The view window allows you to filter the content by event type, date, keyword, etc. You can also download the file by clicking on **Download**.

## Analyzing log files

Log files can be analyzed in order to provide a summary of the activity of JMap Server. For instance, they can inform you of the number of sessions for each user, the number of server shutdowns, authentication failures, etc. To analyze log files, select one or more files in the list and click on .

## Messages

As the administrator, you can send messages to JMap users from JMap Admin. The messages will be displayed in the user interface (JMap Pro applications only). Users who already have an active session will see the messages immediately. The other users will see the message the next time they log on. Messages can be used to inform users of service interruptions, for example. Messages will be displayed each time a user starts a new session, during the validity period of the message.

## Sending messages

To create a new message to be sent to all users, press **Create** from the **Messaging** section.

New message to users	
Subject	A short text describing the subject of the message.
Message	The message itself. Formatting is done using HTML tags. For example, line breaks are done using   tags. The message can contain hyperlinks.
Valid from	The date and time from which the message will start to be displayed.
Valid until	The end date and time from which the message will no longer be displayed. After this date and time, the message will disappear from the list.

## Deleting messages

To delete a message before it expires, select it in the table and press **Delete**.

## JMap Server System Database

JMap Server's System database is a relational database that stores important data for JMap Server. User account and group data is stored in this database if you are using JMap Server's built-in user manager. This is not the case if you are using another user manager (e.g.: LDAP/Active Directory). Also, when spatial data sources read their data from files (SHP, MIF, DWG, etc.), the geometry and descriptive data read from the files are inserted in tables of the System database. There is one data table per such data source, as well as spatial index tables that speed up data extraction. Personal layers created by the users as well as JMap Spatial tables are also stored in the System database.

The relational database management system (RDBMS) used by default for storing JMap Server's System databases is Apache Derby. It is embedded in JMap Server and requires no maintenance. This system is suitable for publishing small to medium spatial data volumes or for test environments. For more robust and powerful systems, you should use another relational database management system. See the list of compatible systems below. By default, Derby's database files are located under the directory **JMAP\_HOME/db/database**. **Never delete or alter any file located in this directory.**

### Moving the JMap Server System database to another environment

JMap Server's System database can be moved to another RDBMS easily. You may want to do it for scalability or performance reasons or to take advantage of more advanced features such as backups. There are 4 other officially supported RDBMS for storing the JMap System database:

RDBMS	Version
MySQL	4.x, 5.x
PostgreSQL	7.2+, 8.x, 9.x
Oracle	8, 9, 10, 11
SQLServer	2000, 2005, 2008, 2012, 2016

Note that other RDBMS and versions will also probably be supported because JMap Server uses mostly very common and simple database functions.

To store the System database, you should use a database or schema that is reserved exclusively for JMap. The user account that established the connection must have sufficient privileges to select, insert, create, and delete tables and indexes.

To move the System database towards another RDBMS, you must modify the database called System in JMap Admin. Select the database driver and connection parameters associated with the environment of the new System database. JMap Server will automatically create the required tables in the new database.

After the System database is moved, any spatial data source that reads vector data files will have a Not ready status. It will need to be updated before it can be used. Other types of data sources (raster, Oracle Spatial, SDE, etc.) will not be affected.

In addition, if you move the System database, all user data from the previous database must be moved using the data import and export tool. For more information, see the [Exporting and Importing](#) section.


## Backups

---

It is strongly recommended to make backups of the JMap Server setup.

If the JMap Server System database was moved to another RDBMS, it must be included in the backup strategy. It contains very sensitive information like personal layers data.

The simpler backup strategy is to make copies of the JMap directory and all sub-directories.



*Contents of the JMap directory*

If you wish to make smaller backups, you can make copies of the specific directories listed below, which contain important information.

Directory	
<b>conf</b>	Contains all parameter files such as jmapserver.properties, usermanager.properties, etc.
<b>db</b>	Contains configuration files (projects, layers, etc.) as well as the JMap Server System database, unless it was moved to another RDBMS.
<b>backups</b>	Default directory for storing export files.
<b>workspaces</b>	User workspaces contain the users' personal parameters and contexts.




## High Availability

---

You can configure clusters of JMap servers to create highly available environments. A highly available JMap environment offers the following benefits:

- Resistant to hardware and software failures.
- Improved performance.
- Improved scalability.
- No service interruptions during software updates.

Clusters of JMap servers (nodes) are peer-to-peer systems with active redundancy. This means that all nodes are equal and synchronized with each other in real time. Each change made to a node's configuration (adding a layer, modifying a form, etc.) is immediately replicated on all of the cluster's nodes.



## Prerequisites for high availability

To configure a JMap installation in high availability mode, including the creation of server clusters, certain prerequisites must be met.

- JMap's System database must be shared by all nodes (preferably in high availability mode).
- A file system must be shared by all nodes to store vector and raster data caches (preferably in high availability mode).
- All nodes must have a JMap license file with the same serial number.
- The IP address linked to JMap Server must be precisely defined. During the installation of JMap, you must enter the IP address of your server that will be linked to JMap Server and not use the default value 0.0.0.0. If necessary, you can run Setup again to change this value or change it

manually in the `JMap/conf/jmapserver.properties` configuration file by editing the line starting with `"server.address ="`. For example `server.address = 208.199.24.134`.

A load balancer is usually present in a high availability architecture. This module is used to send requests to the various nodes in the cluster, in compliance with predetermined rules.

## Creating a cluster of JMap servers

In order to create a cluster of JMap servers, you must have at least 2 instances of JMap Server 7 or higher, connected by a network.

When a new cluster is created, the node that creates the cluster (primary node) is the node whose configuration will be used and replicated on the other nodes when they join the cluster. Make sure you start by configuring the cluster on your server and that your server contains the proper configuration. Afterwards, when a new node will join the cluster, its configuration will be replaced by the cluster's configuration.

The following steps describe how to create a cluster with 2 servers (A and B). Server A contains the proper JMap configuration.

1. The cluster is created on server A.
2. Server A is the primary node, and its configuration becomes the cluster's configuration.
3. Server B becomes part of the cluster.
4. Server B's configuration is replaced by the cluster's configuration.
5. Servers A and B are synchronized in real time.

The primary node concept is only important when the cluster is created. Afterwards, all nodes become equal.

Clusters are configured in JMap Admin, in the Server cluster subsection of the JMap Server section.

Settings	
Enabled	Select this option to enable high availability.
Local ports	Enter a TCP/IP port range to allow the other nodes in the cluster to connect to this server. The default values (47500-47505) can be used, unless this conflicts with other applications.
Node discovery addresses	Enter the TCP/IP addresses of the other nodes in the cluster. It is recommended that each node know the addresses of all the other nodes in the cluster. You must also indicate the TCP/IP ports for each address. If you use the default ports, you can leave this setting unchanged.
Passphrase	Enter the cluster's secret passphrase. All nodes must use the same passphrase to join the cluster. This setting allows you to control access

	to the cluster by other servers on the network. Keep this information confidential.
--	---

When your configuration is complete, click on **Save**. A confirmation window displays, asking you to select one of the two following options. You can also cancel the operation by clicking on **Cancel** in the confirmation window.

Confirmation	
New cluster	Select this option if you want this server to become the primary node of a new cluster. If an existing cluster is found on the network, this action will be canceled in order to prevent this server's configuration from being overwritten by the cluster's configuration.
Join an existing cluster	Select this option if you want this server to join an existing cluster and have its JMap configuration replaced with the cluster's configuration. If no cluster is found, a new cluster is created, and this server becomes the primary node.

## Cluster status

To know the status of the cluster, you can view the list of remote nodes. These are the other nodes that are currently active in the cluster.